Rocket Rider

Charlotte Heibig – Ismael Frei

User guide in the last pages

Systèmes Embarqués Microprogrammés

NDS features: checklist (1/3)

- **ARM Processors**
  - ARM9 to control two screens, some buttons, send IPC messages to ARM7 to control Wifi, touchscreen and sound
- **Timers / Interrupts**
  - Used to restart the game every 12 seconds for added time pressure
- **Graphics**
  - Main screen: Mode 0 with BG 2 (Rotoscale), BG 1 (Tiles) and SPRITES
  - Sub screen: Mode 5 with BG 2 (Rotoscale)
- **Keypad (always read by polling)**
  - While playing level: move the rocket around
  - While creating custom level: move the start and finish point around

©ESL/EPFL

NDS features: checklist (2/3)

- **Touchscreen**
  - While playing level: Change between different levels
  - While creating custom level: control where to put obstacles
- **Sound**
  - Playing music module in a loop when starting the game
  - Playing several sound effects (WAV format) when rocket stops at obstacle, when moving outside of playzone, when finishing

©ESL/EPFL

NDS features: checklist (3/3)

- **Secondary Storage (optional) (Charlotte and Ismael)**
  - Storing the custom level in a txt file
  - Reading a custom level in a txt fille
- **WiFi (optional) (only Ismael)**
  - Send own custom level to another device
  - Receive custom level from another device
- **Sprites (optional) (Charlotte and Ismael)**
  - Rocket is a Sprite that can move freely around. There are 4 pictures of the rocket, one for every direction it flies. The rocket rotates in the direction it will move.

©ESL/EPFL

NDS project screenshot

- **Include an image with the final view/s of your project on the actual NDS device**

Playing Level 2

Modifying custom Level

©ESL/EPFL

User Guide (1/3)

- Start:
  - Choose whether you want to use wifi or not (A,B)(if you chose yes but don’t have available wifi the device wil go into endless search for wifi)

©ESL/EPFL

User Guide (2/3)

- While playing a level:
  - The objective is to get with the rocket into the finish square (orange)
  - You can move with the keypad (UP,DOWN,LEFT,RIGHT)
  - Change level by clicking on one on the touchscreen
  - Press (START) to restart at beginning
  - You only have 12 seconds
  - After 10s the obstacles turn red to show that you only have 2s left
  - When playing CUSTOM level press (SELECT) to change to Modifying Mode

©ESL/EPFL

User Guide (3/3)

- While modifying CUSTOM level:
  - Click on touchscreen grid to make obstacles appear or disappear
  - Move Start and finish with keypad (UP,DOWN,LEFT,RIGHT)
  - Change between Start and Finish with (A)
  - Send your level with (L)
  - Receive a level that was sent by somebody else with (R)
  - Save your level with (X)
  - Load the last saved level with (Y)

©ESL/EPFL