

Projects & project types

Installation, inspection, and mixed projects – how they connect to customers, sites, products, and field workflows.

Step 1

What a project ties together

Customer + Site

+

Product

+

Team

→

Project

→

Assets / Inspections

A project is the container for field work. Two independent axes define behaviour:


- **Project type** – *Internal vs External* (approval workflow).
- **Workflow mode** – *Installation only, Inspection only, or Both (mixed)* (which modules appear on the project detail page).

Routes: list `/projects`, create `/projects/new`, detail `/projects/:id`.

Step 2

Start creating a project

1. Sidebar → **Projects**.
2. Click **Create project** (navigates to `/projects/new`).
3. Page title: *Create project* — subtitle explains identity, scheduling, and installation configuration.
4. Use **Save draft** to persist without submitting, or **Submit project** when ready.



Step 3

Customer & site selection

1. **Customer** – dropdown: *Select existing customer*. Auto-fills **Customer ID** (read-only).
2. **Site** – filtered by customer; format {Customer} - {Site Name}; or *(No site)*.
3. Also capture **Job Number**, **Purchase Order Number**, **Office**, **Project Time Zone**.

Customer

Acme Mining Corp



Customer ID

CUST-0042

Site

Acme Mining Corp - North Pit



Job Number

JOB-2026-118

Step 4

Project type — Internal vs External

Type	Behaviour
Internal	Skips approval; work can begin once the project is in progress.
External	Includes Pending Approval state; requires approval before execution.

External projects show an info alert about the approval workflow. When approved, set **Approval Decision** to *Approved* or *Rejected*.

- ☒ Internal — skips approval
- ☐ External — Pending Approval workflow

Step 5

Workflow mode — installation, inspection, or mixed

Controls which modules are visible on the project detail page.

Mode	UI label	Use when
INSTALLATION_ONLY	Installation only	New installs, commissioning, asset creation from workflows.
INSPECTION_ONLY	Inspection only	Recurring checks; uses project assets and inspection runs; no installation workspace sections.
MIXED	Both (mixed)	Projects needing both install and inspect capabilities on one site.

Workflow mode

Installation only



Inspection-only projects still need a product (for workflow assignment) but hide installation-specific workspace UI.

Step 6

Product & project team members

1. **Product name** — select the primary product from Settings catalog (e.g. HA-Coal Controller). Determines available workflows.
2. **Project Manager** — single user responsible for the project.
3. **Project Team Members** — multi-select active users. These names appear in workflow *User select (project team)* steps at run time.

Product name

HA-Coal Controller



Project Manager

Chris PM



Project Team Members

Alex Technician

Sam Inspector

Jordan Field

Nominate users who can be selected in workflow team-member steps.

Step 7

Status lifecycle & submit

Typical status values:

Draft

In Planning

Pending Approval

Approved

In Progress

On Hold

Completed

Closed

- **Save draft** — keep editing without advancing status.
- **Submit project** — finalise creation; external projects may enter Pending Approval.
- After save, optionally **Copy assets from an existing project** via the clone dialog.
- Assign workflows to assets from the project detail page (see Workflows guide).