

Outlook Express

1. Click on Tools in the menu bar and then go to Accounts



- 2. The Internet Accounts pop-up window appears.
- 3. Click on the Mail tab. If you are starting Outlook Express for the first time, there would not be any email accounts listed on this window.
- 4. To add a new mail account, click Add > Mail.




- 5. Internet Connection Wizard pop-up windows will appear.
- 6. On the Your Name page of the wizard enter your name in the Display name field as you would like it to appear on your outgoing e-mail messages.

7. Click Next to continue.




- 8. The Internet Connection Wizard will now ask for your email address.
- 9. Type in your full e-mail address on the Internet E-mail Address screen, example, eric@hibox.hinet.net
- 10. Click Next to continue.



- 11. In the next window, you need to feed in three important bits of information the incoming and outgoing email servers and the type of the incoming email server.
- 12. On the E-mail Server Names screen, select POP3 from the drop down list.


- 13. In the space provided below Incoming mail (POP3, IMAP or HTTP) server; enter www.hibox.hinet.net
- 14. Type in www.hibox.hinet.net as your Outgoing mail (SMTP) server:
- 15. Click Next to continue.



- 16. The last information that you need to enter to complete the setup of the new account is the user name and password for that email account.
- 17. Account name: Enter your full e-mail address, example, eric@hibox.hinet.net
- 18. Password: Enter your password in the text field.
- 19. Check the box Remember password if you want OE to remember your password.
- 20. Click Next.


Internet Mail Logon		术
Type the account na	me and password your Internet service provider has given you.	
Account name:	eric@hibox,hinet.net	
Password:	NOOR SOUR	
	provider requires you to use Secure Password Authentication haif account, select the "Log On Using Secure Password heck box."	
	re Password Authentication (SPA)	
1 Log on using Secur		

21. Click Finish.



- 22. In the Internet Accounts window ,select the mail account you just created and click "Properties.
- 23. In the Properties window, select the Servers tab.

- 24. Place a check in the My server requires authentication option.
- 25. Click the Settings button.



- 26. In the Outgoing Mail Server box that appears, select Use same settings as my incoming mail server.
- 27. Click OK.

