Euroscope Installation

Euroscope is a very powerful software used for the Air Traffic Controller (ATC) on the Vatsim network. It is important to setup the software correctly, before controlling. It will take some time until you feel familiar with it.

Installation

Downloads - both are required

Visual C++ Redistributable x86:

https://aka.ms/vs/17/release/vc_redist.x86.exe

EuroScope Version 3.2.3.2:


https://euroscope.hu/install/EuroScopeSetup.3.2.3.2.msi

The currently tested and approved EuroScope version is 3.2.3.2.

There are newer versions (3.2.4+), however these versions all have been causing various issues and are not approved for usage in Germany.

Versions 3.2.3 and older will also not work due to new VATSIM authentication requirements. For further information check your respective NAV team's announcements.

Please install the software into a directory of your choice.



Frankfurt Tower - Radar View

Audio for Vatsim (AfV)

To use **voice communication** you have to install the additional software <u>Audio for Vatsim</u>. After that, run the software and check the settings for your audio devices and enter your ID and password. While controlling, it's recommended to run the software as administrator to work correctly in the background.

For **push to talk** we recommend the **left ctrl (Strg)** button at your keyboard.

If you have a primary frequency set in Euroscope, AfV will set it's frequency automatically after clicking on "connect".


Initial Setup

After installing the software you still need the sectorfile, where you get all local data from you need for controlling. Additional to the sectorfile we offer a variety of files and plugins pre installed, so that this package is ready to use for you. You can download the different packages for each FIR at files.aero-nav.com/EDXX.

Download the package and create a folder anywhere you like (recommended at C:\Users\me\Documents\EuroScope). For a better overview we recommend to name the folder according to the FIR where the data is coming from (EDGG, EDMM or EDWW). Copy all provided data into the folder in the same structure as download, as it will not work otherwise!

Select a Profile: After you've done the above steps, you can open Euroscope and you are prompted to select a profile (.prf file). Choose one of the provided ones and you are ready to use Euroscope and all it's features. Different views and airports are already predefined. Therefore you have to click on "OPEN SCT" in the green colored menu bar and select one of the listed .asr files or load one of other provided files via the "Open..." menu.

```
DDF PHX TWR
                                        18:52:30
                             DLH7JA
                   Sector Menu
Download Sector Files ...
EDDF PHX TWR.asr
EDDF_PHX_GND.asr
EDDL_PHX_TWR.asr
EDDL_PHX_GND.asr
EDDS_PHX_TWR.asr
EDDS_PHX_GND.asr
EDDK_PHX_TWR.asr
EDDK_PHX_GND.asr
Open ...
 ...
Save
Save as ...
New radar display
Load Sector File
Load Aliases
Load ICAO Airlines data
Load ICAO Airports data
Load ICAO Aircraft data
Load Load airport coordinates (ICAO.txt)
Load FSNavigator data
Load VATSIM server IP addresses
Load additional server IP addresses
About EuroScope
```



Open a new .asr file for different views

Disable "auto load" and "auto save"

If you would like to open a different profile over the time or you have some problems with different views (e.g. you have choosen the "wrong" profile), it's highly recommended to disable the "Auto load last profile on startup" and "Auto save profile on exit" items to always select the profile manually.


You can find these options at **OTHER SET** at the top menu bar of Euroscope.

Login as Observer

You can always login as observer (OBS). Open your profile of choice and click on "Connect" at the upper left corner. As Callsign we suggest to use *XX_OBS* with XX replaced by your initials (the _OBS at the end is required). Enter your ID and password, check your rating (probably observer), choose your server and you can connect to Vatsim.

Listen to the Frequency: In order to listen to other controllers, you have to open AfV and click on connect thereafter. Then you need to click on the small "+" to enter the station Login into the

search window you would like to listen to (e.g. EDDF_S_TWR). You will get a selection of frequencies to listen to. Click on *RX* and you will hear the controller and the pilots on that frequency.




Audio for Vatsim when logged in as Observer

Select the active airport and runways: It is also recommended to activate the airport and it's select runways. Only if the airport is selected, you can see information in the different lists (e.g. you will only see Frankfurt departures in the departliste list, if EDDF is activated). Simply click on the runway symbol at the menu bar at the top, activate the airport for ARR and DEP, chose the runway and you can see everything the controller sees as well.

Reset visual point: If you can't see any traffic as Observer even if there should be some, it might be your visual point is to far away from the airport you are looking at.

To reposition your center of view, enter .vis into the command line at the bottom and click into the scope. Your center of view is repositioned thereafter.



Euroscope connection dialog when login as Observer

Version #20

Erstellt: 9 August 2022 07:43:50

Zuletzt aktualisiert: 1 September 2024 17:18:28 von 1586741