



GigaCloud


Software Licensing Guide

July 2019

GigaCloud Licensing

Licensing allows you to request **GigaTrust Desktop Client** and **Dynamic File Folders** licenses and upload them into GTEP to manage them. You can manage licensing in the GTEP Configuration Tool or in GigaCloud Administration.

To manage licensing in the Configuration Tool, open the GTEP Configuration Tool from your server desktop and go to the **Server > Licensing** node.



Select **Request** and the following window is displayed:


The 'Request a License' dialog box contains the following fields and options:

- Full Name: John Smith
- Company Name: Acme Inc.
- Email: jsmith@acme.local
- Enterprise User Count: ☒ Unlimited
- External User Count: ☒ Unlimited
- File Folders Count: ☐ Unlimited, 12
- Expiration: ☒ Perpetual, Saturday, December 1, 2018


Buttons at the bottom: Download, Submit, Cancel.

1. Enter your **Full Name**, **Company Name** and **Email** where you would like the licenses sent.
2. Choose **Unlimited** for Enterprise Users, External Users and/or File Folders or enter a specific number of licenses for each one.
3. Select **Perpetual** for licenses that never expire or select an expiration date.
4. Select **Submit** and you should receive an email shortly with a license file attached. If you do not have external access to send an email from the server, select **Download** and a request will be downloaded. Attach the request and send on an email accessible pc to request a license.
5. After you receive the license file select **Upload**, select the file and click save. The number and type of licenses you requested will be displayed in the pane.

To manage licensing in GigaCloud, open GigaCloud Administration and go to the **Cloud Administration** ➤ **Licensing** node.



- Select **Request License** to create a request for GigaTrust to obtain licenses and the following form is displayed:

A screenshot of a web form titled "Request License" with a close button (X) in the top right corner. The form contains several input fields and checkboxes. The fields are: *Full Name (text input with "John Smith"), *Company Name (text input with "Acme Inc."), *Email (text input with "jsmith@acme.com"), *Enterprise User Count (checkbox checked, "Unlimited", and an empty text input), *External User Count (checkbox unchecked, "Unlimited", and text input with "33"), *File Folder Count (checkbox checked, "Unlimited", and an empty text input), and *Expiration (checkbox checked, "Perpetual", and an empty text input). At the bottom, there are three buttons: "Close" (with an X icon), "Download License Request" (with a cloud icon), and "Request License" (with a document icon).

1. Enter your **Full Name**, **Company Name** and **Email** where you would like the licenses sent.
2. Choose **Unlimited** for Enterprise Users, External Users and/or File Folders or enter a specific number of licenses for each one.
3. Select **Perpetual** for licenses that never expire or select an expiration date.
4. Select **Request License** and you should receive an email shortly with a license file attached. If you do not have external access to send an email from the server, select **Download License Request** and a request will be downloaded. Attach the request and send on an email accessible pc to request a license.

- After you receive the license file select **Upload License** and the following form will be displayed:

Upload License

Browse...

Close

Upload

- Select the file and click **Upload**. The number and type of licenses you requested will now be displayed in the main pane as shown below.

GigaTrust

Welcome

Dashboard

Organization

Users

Groups

Administrators

Summary

Sync Agent Log

Block Access

Revoke Access

Configuration

Cloud Administration

Licensing

Tenants

Software

Email Tenants

Tenant Event Log

Client Errors

Configuration

Home > Cloud Administration > Licensing

LICENSING | manage software licenses for GigaCloud

Upload License

Request License

Refresh

Licensing

Enterprise Licenses	unlimited
Enterprise Users	3
Enterprise Overage	2
External Licenses	unlimited
External Users	0
External Overage	2
DFF Licenses	unlimited
Expiration	perpetual

Label Definitions

Enterprise Licenses – number of licenses available for Enterprise GTDC for users.

Enterprise Users – current number of users with Enterprise GTDC installed.

Enterprise Overage – number of users over the Enterprise License limit.

External Licenses – number of licenses available for External GTDC for users.

External Users – current number of users with GTDC installed externally.

External Overage – number of users over the External License limit.

DFF Licenses – number of Dynamic File Folders licenses available.

Expiration – expiration date of all licenses.