

TNE20003 – Internet and Cybersecurity for Engineering Applications

Portfolio Task - Lab 3 Pass Task

Aims:

- To understand how arp works
- To investigate how MAC addresses are used and how the CAM table in a switch is populated.

Preparation:

View "Network Devices - Routers and Switches"

Due Date:

All tasks in this lab are to be completed and demonstrated to your Lab instructor preferably during
or at the end of the current lab, but if you do not complete the tasks you may demonstrate it at the
beginning of your next lab class.




Task 1.

Practice Subnetting

In this task, you will

• Subnet the given network (n/w) in the diagram below and allocate a subnet address to each relevant segment.



What is the subnetwork address of the IP given above???? Subnet mask: /19: 255.255.224.0 Subnet address: 150.100.120.0

How many n/ws do we need to build this n/w? _____6 networks

How many bits need to be borrowed? 3 bits, since $2^3 - 2 = 6 = 6$ networks

What do the dotted lines connecting 2 routers mean?

The link connection, or Point-to-Point connection, that enables the routers to communicate and share routing informations as a part of a larger network infrastructure



Task 2.

Build the network provided in task 1 with Cisco Packet Tracer and observe the building of ARP tables in the PCs and CAM table in the switch

1. Implement the network shown in figure 1 above.

The bottom left hand corner of the Packet tracer screen displays the icons that represent device categories or groups, such as **Routers**, **Switches**, or **End Devices**.

Moving the cursor over the device categories will show the name of the category in the box. To select a device, first select the device category. When the device category is selected, the options within that category appear in the box next to the category listings. Select the device option that is required.

- a. Select **End Devices** from the options in the bottom left-hand corner. Drag and drop 4 PCs and 1 Server onto your design area.
- b. Select **Switch** from the options in the bottom left-hand corner. Add 2 2960 switches to your prototype network by dragging them onto your design area.
- c. Select **Router** from the options in the bottom left-hand corner. Add 4 2911 routers to your prototype network by dragging them onto your design area
- d. Double click on each of the devices and name them as per the network diagram in figure 1.
- e. Select **Connections** from the bottom left-hand corner. Choose a copper straight-through cable type. Click the first PC (PC1) and assign the cable to the **FastEthernet0** connector. Click the switch (LS1) and select **FastEthernet0/1** to connect to PC1.
- f. Select Connections from the bottom left-hand corner. Choose a copper straight-through cable type. Click the second PC (PC2) and assign the cable to the FastEthernet0 connector. Click LS1 and select FastEthernet0/2 to connect to PC2.
- g. Select Connections from the bottom left-hand corner. Choose a copper straight-through cable type. Click the third PC (PC3) and assign the cable to the FastEthernet0 connector. Click LS1 and select FastEthernet0/3 to connect to PC3.
- h. Select **Connections** from the bottom left-hand corner. Choose a copper straight-through cable type. Click the switch (LS1) and select **FastEthernet0/4** to connect to **GigabitEthernet0/0** of Rtr1.
- i. Repeat these steps for all of the other devices until they are all connected as per the n/w diagram in figure 1. Note when connecting 2 routers together you need to use a cross-over cable because they are like devices, ie both are DTEs. Or you can use a serial cable.



There should be green dots at both ends of each cable connection after the network has converged. If not, double check the cable type selected. Note with the routers in particular, you may need to turn that interface on by clicking the "on" button under the interface tab or by issuing the command "no shut" on the interface in the CLI mode. See below:


```
Router*
Router*
Router*
Router*
Configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)*interface GigabitEthernet0/0
Router(config-if)*no shut
```

2. Configure Host names and IP Addresses on the PCs, the Server, the switches and the routers

- a. Click PC1. Select the Config tab. Change the PC Display Name to LAN1_PC1. Select FastEthernet tab on the left and add an IP address and subnet mask from your calculated available networks. Close LAN1_PC1 when done.
- b. Click PC2. Select the Config tab. Change the PC Display Name to LAN1_ PC2. Select FastEthernet tab on the left and an IP address and subnet mask from your calculated available networks. Close LAN1_PC2 when done.
- c. Click PC3. Select the Config tab. Change the PC Display Name to LAN1_PC3. Select FastEthernet tab on the left and add an IP address and subnet mask from your calculated available networks. Close LAN1_PC3 when done.
- d. Click PC4. Select the Config tab. Change the PC Display Name to LAN2_PC1. Select FastEthernet tab on the left and add an IP address and subnet mask from your calculated available networks. Close LAN2_PC1 when done.
- e. Click Server0. Select the Config tab. Change the Server Display Name to FileServer. Select FastEthernet tab on the left and add an IP address and subnet mask from your calculated available networks. Close FileServer when done.
- f. Name the 2 switches as they are in figure 1.
- g. Name all the routers as they are in figure 1 and choose a relevant address for each interface from the relevant subnet.



- 3. On each PC observe the current status of the ARP table by issuing the following command and note what is displayed.
 - a. Click on the PC and choose "desktop" and then click on the "command prompt"



- b. In the "command prompt" window type "arp -a"
- c. Note what is displayed.
- 4. On the switch LS1 issue the following commands to see what is stored in the CAM table
 - a. Choose the CLI mode
 - b. Click enter until you see the following prompt: Switch>
 - c. Type "enable"
 - d. Type "show arp" what do you see? See pic below for guide
 - e. You can investigate the CAM table of the switch by typing "show mac address-table". what do you see?



- f. Whose MAC address could this be?
- g. Before you leave the switch type the following commands to make sure it stays in the privileged mode of operation. See pic below for commands and steps.

```
LS1>enable
LS1‡configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
LS1(config)‡line console 0
LS1(config-line)‡exec
LS1(config-line)‡exec-timeout 0 0
LS1(config-line)‡
```

- 5. If want to observe the flow of data in PT between LAN_PC1 and LAN_PC2 follow the commands below or jump to step 6.
 - a. Switch to **Simulation Mode** in the bottom right-hand corner.
 - b. Click **Edit Filter** in the **Edit List Filter** area. In the event list filter, *only select* **ARP** and **ICMP** filters under IPv4 tab, deselect all other filters in the three tabs **IPV4**, **IPV6** and **Misc**.
 - c. Select a Simple PDU by clicking the closed envelope in the upper toolbar.With the envelop icon, click LAN_PC2 to establish the source. Click LAN_PC1 to establish the destination.
- Using the IP addresses you have configured previously, ping LAN_PC1 from LAN_PC2.
 Note that if you have carried out step 6 above you do NOT need to do part (a) below.
 - a. Click on LAN_PC2 and from the Desktop link choose the Command Prompt and type the following command when you see the prompt C:\>"ping (put the IP address of LAN_PC1 here)" and you should see something similar to the pic below



```
C:\>ping 192.168.10.1

Pinging 192.168.10.1 with 32 bytes of data:

Reply from 192.168.10.1: bytes=32 time<1ms TTL=128

Ping statistics for 192.168.10.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```

- b. Repeat steps 3 and 4 above to see if any of the tables have changed.
- After PC2 and PC1 are ping-ed, the CAM table in the switch has . What did you observe? Explain it in your own words. observed the MAC address of both PC-A and PC-B while both PC has each other IP Address and MAC Address
- d. What happens to the CAM table in LS1 if you don't do anything for a period of time?

 The CAM Table will refresh and listen to new MAC Addresses. The reason why CAM Table has to refresh is to ensure the memory optimisation, dynamic MAC allocation and security
- 7. Using the IP addresses you have configured previously, ping from LAN_PC2 ping all of the other PCs including the server.
 - a. Click on LAN_PC2 and from the Desktop Command Prompt type "ping (put the IP address of LAN_PC3 here)".
 - b. Click on LAN_PC2 and from the Desktop Command Prompt type "ping (put the IP address of R1 interface connected to the switch)". Was the ping successful? Explain why or why not.
 - c. Click on LAN_PC2 and from the Desktop Command Prompt type "ping (put the IP address of LAN_PC4 here)" Was the ping successful? Explain why or why not.
 - d. Click on LAN_PC2 and from the Desktop Command Prompt type "ping (put the IP address of the Server here)" Was the ping successful? Explain why or why not.
 - e. Repeat steps 3 and 4 above to see if any of the tables have changed.
 - f. What did you observe? Explain it in your own words.

The CAM table only shows the MAC Address of PC2, PC3 and Router1. Since it is the only devices that the LS1 switch are able to capture the MAC Address and the routers are not routed yet thus making devices on network A can not ping the devices on network F (based on diagram)

~~~~ End of Lab ~~~~

b,c,d: NO, although the PC2 are able to send ARP and ICMP package to LS1 switch and Router1, but the router could not be able to transmit the package to the Router4 because the routers are not CONFIGURED ROUTING thus unable to send the packages through multiple networks