The Minemaker

1.Introduction

The Minemaker is a very powerfull tool for creating mines for box servers or personal usage. It’s almost 100% GUI based, meaning there is not additional coding or much command use, you just click in the GUI. It uses a smart registry system which unitized all the mines and makes it super easy to delete or just remove the mines from the registry, reseting the mines and editing them.

2.How to use:

To start using the Minemaker, use the command /minemaker and the tool should be in your inventory. You can then open the GUI by right clicking with the tool in your hand.

2.1 Setting the region (position 1 and position 2)

To set the region of the mine, you select the opposite corners, just like in WorldEdit. To set Position 1, you either Left click the block that you want to be the first corner with the Minemaker in your hand, or open the GUI and click the "Pos 1" slot, which will set the first corner to the position of the player. Then to set Position 2, you either shift right click the block that you want to be the second corner with the Minemaker in your hand, or open the GUI and click the "Pos 2" slot which sets the second corner to the position of the player. Now you have selected the region of the mine you are creating.

2.2 Setting the name of the mine

To set the name of the mine, open the GUI and click the nametag on the top, this will open a sign GUI where you will type in the name you want to use and after you finish typing you click done. This name will be used as an identificator of the mine, by that name it will be saved into registry and u will later be able to use it to edit, delete or reset the mine. Now only the first line of the sign GUI will actually be the name, be aware of that.

s

To set the blocks the mine will contain, click the Pick a Block item in the main GUI, and a new GUI named Block picker should open. In the Block picker, you should see 9 slots in the middle. The first row is used for picking the actual containement of the mine, each column of that row is an individual block, just put some item of a block of your liking in the slots (starting with the left one, you can leave the rest empty), then after youve picked your desired blocks, for each block you can assign the chance it has of spawning in the mine by clicking the gold ingot named Chance under that block. When you left click, it adds 1% to the chance, when you shift left click, it adds 10%, when you right click it subtracts 1% and when you shift right click it subtracts 10%. After you’ve picked your blocks and their chances, now you can pick what that block will give the player when it

gets mined, again in the same column right under the gold bar, place an item of your liking, the amount of items you put in that slot will decide how many of those items the player will get.
After you are finished with everything, click the green concrete in the right corner to save the data!

Example:



In this example, the mine will be fully made out of spruce logs and after mining one log the player will get 3 coarse dirt.

2.3 Setting the Compression Chains

Compression of blocks means that after you mine some amount of some block, it will get automatically “compressed“ into a higher tier item. You can set up this system with by clicking the Compression item in the main GUI, after that another GUI should open, it should be named Compressions. Here we have 3 rows, each row is a different independent Compression Chain. To set up this chain, start putting items of your choice slot by slot from left to right (again there is no problem with leaving some slots empty), it compresses the items from left to right using the amount of items you put in. And you can do this 3 times for each chain. A chain ends at the end of the row
After you are done, click the green concrete again.



In this example: There are 64 of tier 0 item in the first slot, 32 of tier 1 item in the second and 16 of tier 2 in the third slot (the rest are empty). After the player has 64 of tier 0 items in their inventory, the items get compressed into ONE tier 1 item, after the player gets 32 tier 1 items, they get compressed into ONE tier 2 item, and since the rest are empty, they will just keep getting tier 2 items forever, even if there are more than 1 of the last item.

2.4 Setting the Mine Monster

To set the spawning of a Mine Monster in your mine, click the Mob picker item in the main GUI, a Mob picker GUI should open. Now a Mine Monster is a customisable mob that will spawn in your mine with some chance, after it gets killed it drops the amount of blocks it took to spawn it, meaning the amount of blocks mined between two mob spawns. This part is fully optional and if you do not want any mob spawning in your mine, just leave the mob type empty. If you do want the mob spawning, continue.

2.4.1 Mob type

To pick the type of the mob you would like to spawn, click on the zombie head in the Mob picker GUI and a sign GUI will open, there type in your desired mob you want to spawn in the mine (for example “zombie“) and click done. If you put your cursor over the mob head again, it should say Mob type is: “your mob type“, if it doesnt say anything after Mob type is:. It means you put in an invalid mob type, if that happens, nothing breaks, it just means no mob will spawn at all, click the head again and try it once more. If it does say the correct mob type, continue.

2.4.2 Mob name

To pick the mob name, in the Mob picker GUI click the name tag and a sign GUI should open again, here you can put any text at all, whatever text you put in will display over the mob after it gets spawned, you can even use the minecraft colour codes before the name (for example &c for red). You cannot make the name too long, if your picked name overflows to the second line, that line wont count and it will only set the first line as the name. Again hover your mouse over the name tag and you should see you picked name there.

2.4.3 Mob spawning chance

To set the mob spawning chance, click the mossy cobblestone in the Mob picker GUI. After that yet another sign pops up, here type in a number, it can be decimal too, this number will represent the chance of the mob spawning after each mined block in percentage (for example with 50% the mob will spawn approximately every 2 blocks mined). Click done again and hover your cursor over the mossy cobblestone, if you dont see any value after Mob spawning chance:, that means you didnt put in a valid number, click the cobblestone again and try it one more time, if you dont put in a valid number the mob wont spawn.

2.4.4 Mob health, strength, resistance, speed

To set each, click the slot of each and again, set the number you want each to be, health will be based to 20 HP if you dont put in a valid number and each of the effects will get based to 0 if you dont put in a valid number.

2.4.5 Mob armour and tools

For last, to set the mob armour and tools, use the empty slots in the second row, the first slot is for the main hand of the mob (the item the mob will be holding in the main hand), the second slot is for the offhand (the item the mob will be holding in the offhand), the third slot is helmet, fourth is chestplate, fifth is leggings and the last empty slot is boots. You can put in any item at all in the main and offhand slots, for armour slots it has to be armour. Now to enchant the armour you can set the protection value using the enchanted book, after clicking it another sign GUI will open up and there put in a number representing the level of protection of each armor piece. Be aware that if you set the protection level after youve put in the armour and tools, they will get reset to empty slots. If you leave any of the slots empty, the mob just wont spawn with that part. And if you dont put in a valid number in the protection slot, it will base to 0.

2.5 Creating the mine and later adjustements

After youve set everything you want your mine to have, you can click the green concrete in the main GUI and the mine should get created where you set it to. Now you can test the mine out! It automatically resets when the blocks are low and also resets every 40 seconds. You can also manually reset the mine by doing ***/resetmine <name of your mine>***, if you forgot the name of your mine, you have two choices, you can either run ***/resetmine all***, which resets all registered mines, or you can check the name of your mine in ***/mineslist***, which sends a list of all the registered mines in chat, there you can find the name of your mine. Now, if you forgot to add something or accidentaly put in a wrong value or item somewhere, dont panic. Remember the name of the mine and run ***/mineslist edit <name of your mine>***, this temporarily removes the mine from the world, so dont get scared, but now if you reopen the Minemaker tool GUI, all the data of that mine has been saved into your tool and you can change your value and then click Create Mine again, which will spawn the mine back if the adjusted values. Also if you accidentally clicked the Reset button, dont panic either, since the mine only got deleted on the physical part, it is still saved in ***/mineslist***, so you can just run ***/mineslist edit <name of your mine>*** again to start editing it again.
For the last, if you dont like your mine anymore or need it removed, you can run ***/removemine <name of your mine>*** to remove your mine from the Mineslist, or you can also do ***/removemine all*** to remove all of the mines registered, this will not delete the physical part though, so if you want it to be deleted from the world fully, just add **delete** after each command for removing. Now check ***/mineslist*** again and the mine wont be registered anymore.

This should be all the information needed to work with the Minemaker tool, if you have any additional questions, dont be scared to ask!!!