Local compiler switches

			•
cmd	short	long	explanation
	A	\$ALIGN	Align Data.
A		\$ASMMODE	Select assembler mode.
	B	\$BOOLEVAL	Use complete boolean evaluation.
Sa	C	\$ASSERTIONS	Enable assertion support.
		\$CALLING	Set default calling convention
d		\$DEFINE	Define a symbol.
		\$ELSE	Switch conditional compilation.
		\$ENDIF	End conditional compilation.
		\$ERROR	Generate error message.
	F		Use far or near functions.
		\$FATAL	Generate fatal error message.
Sg		\$GOTO	Support Goto and Label.
	H	\$LONGSTRINGS	Use AnsiStrings.
		\$HINT	Generate hint message.
vh		\$HINTS	Emit hints
		\$IF	Start conditional compilation.
		\$IFDEF	Start conditional compilation.
		\$IFNDEF	Start conditional compilation.
		\$IFOPT	Start conditional compilation.
		\$INFO	Generate info message.
Si		\$INLINE	Enable inline code support.
Ci	\$I	\$IOCHECKS	Include Input/Output checking.
	\$I	\$INCLUDE	Include file.
	\$I	\$INCLUDE	Include compiler info.
	L	\$LINK	Link object file.
		\$LINKLIB	Link to a library.
	M	\$TYPEINFO	Generate Run-Time type information.
Sm		\$MACRO	Enable macro support.
		\$MAXFPUREGISTER	set maximum number of FPU registers
		\$MESSAGE	Generate info message.
		\$MMX	Enable Intel MMX support.
		\$NOTE	Generate note message.
vn		\$NOTES	Emit notes.
A		\$OUTPUT_FORMAT	Select compiler output format.
	\$ P	\$OPENSTRINGS	Use open strings.
		\$PACKENUM	Specify minimum enumeration type size.
		\$PACKRECORDS	Specify Alignment of record elements.
Co	\$Q	\$OVERFLOWCHECKS	Use overflow checking.
Cr	\$R	\$RANGECHECKS	Use range checking.
		\$SATURATION	Enable saturation operations.
XX		\$SMARTLINK	Use smartlinking.
St		\$STATIC	Enable use of Static keyword.
		\$STOP	Generate fatal error message.
	T	\$TYPEDADDRESS	Enable typed address operator.
u	. –	\$UNDEF	Undefine a symbol.
u	\$V	\$VARSTRINGCHECKS	Use strict var-string checking.
	¥ *	\$WAIT	Wait for enter key press.
		\$WARNING	Generate warning message.
		\$WARNINGS	Emit warnings.
	\$ X	\$EXTENDEDSYNTAX	Enable use of extended syntax.
	ΨΔΥ	ATVITIONDOLLIVIV	Enable use of extended symbox.

${\bf Global\ compiler\ switches}$

\mathbf{cmd}	\mathbf{short}	long	explanation
		\$APPID	Set application ID (PalmOS)
		\$APPNAME	Set application name (PalmOS)
		\$APPTYPE	Specify type of application (Windows only)
g	D	\$DEBUGINFO	Include debugging symbols.
		\$DESCRIPTION	Not supported.
	E		Enable emulation of coprocessor.
	G		Generate 80286 code.
Fi		\$INCLUDEPATH	Specify include file search path.
	L	\$LOCALSYMBOLS	Enable local symbol information.
Fl		\$LIBRARYPATH	Specify library search path.
	M	\$MEMORY	Specify memory sizes.
\mathbf{M}		\$MODE	Specify compiler compatibility mode.
	N		Enable numeric processing.
	\$O		Enable overlay code generation.
Fo		\$OBJECTPATH	Specify object file search path.
Ct	S		Use stack checking
Fu		\$UNITPATH	Specify unit file search path.
		\$VERSION	Set DLL version (Windows)
	W	\$STACKFRAMES	Generate stackframes.
_b	\$Y	\$REFERENCEINFO	Insert browser information.