ThermalModel

5.0

Generated by Doxygen 1.8.14

Contents

1	Mod	odule Index	1
	1.1	1 Modules	 1
2	Nam	amespace Index	3
	2.1	1 Namespace List	 3
3	Hier	ierarchical Index	5
	3.1	1 Class Hierarchy	 5
4	Data	ata Structure Index	7
	4.1	1 Data Structures	 7
5	File	le Index	9
	5.1	1 File List	 9
6	Mod	odule Documentation	11
	6.1	1 Models	 11
		6.1.1 Detailed Description	 11
	6.2	2 Interactions	 12
		6.2.1 Detailed Description	 12
	6.3	3 ThermalRider	 13
		6.3.1 Detailed Description	 13
		6.3.2 Macro Definition Documentation	 13
		6.3.2.1 PATH	 13

ii CONTENTS

7	Nam	espace	Documer	ntation	15
	7.1	jeod Na	amespace	Reference	15
		7.1.1	Detailed	Description	15
8	Data	Structi	ure Docun	nentation	17
	8.1	jeod::T	hermalFac	cetRider Class Reference	17
		8.1.1	Detailed	Description	18
		8.1.2	Construc	tor & Destructor Documentation	18
			8.1.2.1	ThermalFacetRider() [1/2]	19
			8.1.2.2	~ThermalFacetRider()	19
			8.1.2.3	ThermalFacetRider() [2/2]	19
		8.1.3	Member	Function Documentation	19
			8.1.3.1	accumulate_thermal_sources()	19
			8.1.3.2	initialize()	19
			8.1.3.3	integrate()	20
			8.1.3.4	operator=()	20
		8.1.4	Friends A	And Related Function Documentation	20
			8.1.4.1	init_attrjeodThermalFacetRider	20
			8.1.4.2	InputProcessor	21
		8.1.5	Field Doo	cumentation	21
			8.1.5.1	active	21
			8.1.5.2	cycle_time	21
			8.1.5.3	d_temperature	21
			8.1.5.4	dynamic_temperature	22
			8.1.5.5	emissivity	22
			8.1.5.6	facet	22
			8.1.5.7	heat_capacity	22
			8.1.5.8	integrable_object	23
			8.1.5.9	next_temperature	23
			8.1.5.10	power_absorb	23
			8.1.5.11	power_emit	23

CONTENTS

		8.1.5.12	rad_constant	24
		8.1.5.13	stefan_boltzmann	24
		8.1.5.14	thermal_power_dump	24
8.2	jeod::T	hermalInte	egrableObject Class Reference	25
	8.2.1	Detailed	Description	26
	8.2.2	Construc	etor & Destructor Documentation	26
		8.2.2.1	ThermalIntegrableObject() [1/2]	26
		8.2.2.2	~ThermalIntegrableObject()	26
		8.2.2.3	ThermalIntegrableObject() [2/2]	27
	8.2.3	Member	Function Documentation	27
		8.2.3.1	compute_temp_dot()	27
		8.2.3.2	create_integrators()	27
		8.2.3.3	destroy_integrators()	27
		8.2.3.4	get_temp()	28
		8.2.3.5	get_temp_dot()	28
		8.2.3.6	initialize()	28
		8.2.3.7	integrate()	29
		8.2.3.8	operator=()	29
		8.2.3.9	reset_integrators()	29
	8.2.4	Friends A	And Related Function Documentation	30
		8.2.4.1	init_attrjeodThermalIntegrableObject	30
		8.2.4.2	InputProcessor	30
	8.2.5	Field Doo	cumentation	30
		8.2.5.1	active	30
		8.2.5.2	integrator	30
		8.2.5.3	rider	31
		8.2.5.4	t_pow4	31
		8.2.5.5	temp	31
		8.2.5.6	temp_dot	31
8.3	jeod::T	hermalMe	essages Class Reference	32

iv CONTENTS

	8.3.1	Detailed D	Description	32
	8.3.2	Constructo	or & Destructor Documentation	32
		8.3.2.1	ThermalMessages() [1/2]	32
		8.3.2.2	ThermalMessages() [2/2]	32
	8.3.3	Member F	unction Documentation	33
		8.3.3.1	operator=()	33
	8.3.4	Friends Ar	nd Related Function Documentation	33
		8.3.4.1	init_attrjeodThermalMessages	33
		8.3.4.2	InputProcessor	33
	8.3.5	Field Docu	umentation	33
		8.3.5.1	incomplete_setup_error	33
		8.3.5.2	invalid_integration_operation	34
8.4	jeod::Tl	hermalMod	elRider Class Reference	34
	8.4.1	Detailed D	Description	35
	8.4.2	Constructo	or & Destructor Documentation	35
		8.4.2.1	ThermalModelRider() [1/2]	35
		8.4.2.2	~ThermalModelRider()	35
		8.4.2.3	ThermalModelRider() [2/2]	35
	8.4.3	Member F	unction Documentation	35
		8.4.3.1	operator=()	36
		8.4.3.2	update()	36
	8.4.4	Friends Ar	nd Related Function Documentation	37
		8.4.4.1	init_attrjeodThermalModelRider	37
		8.4.4.2	InputProcessor	37
	8.4.5	Field Docu	umentation	37
		8.4.5.1	active	37
		8.4.5.2	include_internal_thermal_effects	38
8.5	jeod::Tl	hermalPara	ıms Class Reference	38
	8.5.1	Detailed D	Description	39
	8.5.2	Constructo	or & Destructor Documentation	39
		8.5.2.1	ThermalParams() [1/2]	39
		8.5.2.2	\sim ThermalParams()	39
		8.5.2.3	ThermalParams() [2/2]	39
	8.5.3	Member F	unction Documentation	39
		8.5.3.1	operator=()	39
	8.5.4	Friends Ar	nd Related Function Documentation	40
		8.5.4.1	init_attrjeodThermalParams	40
		8.5.4.2	InputProcessor	40
	8.5.5	Field Docu	umentation	40
		8.5.5.1	emissivity	40
		8.5.5.2	heat_capacity_per_area	40
		8.5.5.3	thermal_power_dump	40

CONTENTS

9	File I	Documentation	41
	9.1	class_declarations.hh File Reference	41
		9.1.1 Detailed Description	41
	9.2	thermal_facet_rider.cc File Reference	41
		9.2.1 Detailed Description	42
		9.2.2 Macro Definition Documentation	42
		9.2.2.1 pow4	42
	9.3	thermal_facet_rider.hh File Reference	42
		9.3.1 Detailed Description	42
	9.4	thermal_integrable_object.cc File Reference	43
		9.4.1 Detailed Description	43
	9.5	thermal_integrable_object.hh File Reference	43
		9.5.1 Detailed Description	43
	9.6	thermal_messages.cc File Reference	44
		9.6.1 Detailed Description	44
	9.7	thermal_messages.hh File Reference	44
		9.7.1 Detailed Description	44
	9.8	thermal_model_rider.cc File Reference	45
		9.8.1 Detailed Description	45
	9.9	thermal_model_rider.hh File Reference	45
		9.9.1 Detailed Description	45
	9.10	thermal_params.cc File Reference	45
		9.10.1 Detailed Description	46
	9.11	thermal_params.hh File Reference	46
		9.11.1 Detailed Description	46
Inc	dex		47

Module Index

1.1 Modules

Here is a list of all modules:

Models	11
Interactions	 12
ThermalRider	 13

2 Module Index

Namespace Index

2.1	Namespace	List

riere is a list of all flamespaces with brief t	descriptions.	
jeod		

4 Namespace Index

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

ntegrableObject	
jeod::ThermalIntegrableObject	25
eod::ThermalFacetRider	17
eod::ThermalMessages	32
eod::ThermalModelRider	34
eod::ThermalParams	38

6 Hierarchical Index

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

jeod::ThermalFacetRider	
Defining the thermal characteristics of surface facets	17
jeod::ThermalIntegrableObject	
Encapsulates a thermal integrator for a facet	25
jeod::ThermalMessages	
Specifying the message IDs used in the model	32
jeod::ThermalModelRider	
Defining the thermal functionality	34
jeod::ThermalParams	
A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-	
model facets in their respective InteractionSurfaceFactorys	38

8 Data Structure Index

File Index

5.1 File List

Here is a list of all files with brief descriptions:

class declarations.hh	
Forward declaration of classes defined in Thermal_rider model	41
thermal facet rider.cc	
ThermalFacetRider interaction model	41
thermal facet rider.hh	
Defining the thermal characteristics of surface facets	42
thermal integrable object.cc	
Encapsulates an integrator for a single facet	43
thermal_integrable_object.hh	
Define an IntegrableObject class adapted to thermal integration	43
thermal_messages.cc	
Implement the class ThermalMessages	44
thermal_messages.hh	
Define the class ThermalMessages, the class that specifies the message IDs used in the model	44
thermal_model_rider.cc	
ThermalModelRider interaction model	45
thermal_model_rider.hh	
Defining the thermal functionality	45
thermal_params.cc	
Thermal Parameter definition	45
thermal_params.hh	
A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-	
model facets in their respective InteractionSurfaceFactorys	46

10 File Index

Module Documentation

6.1 Models

Modules

Interactions

6.1.1 Detailed Description

12 Module Documentation

6.2 Interactions

Modules

ThermalRider

6.2.1 Detailed Description

6.3 ThermalRider 13

6.3 ThermalRider

Files

· file class_declarations.hh

Forward declaration of classes defined in Thermal_rider model.

• file thermal_facet_rider.hh

Defining the thermal characteristics of surface facets.

• file thermal_integrable_object.hh

Define an IntegrableObject class adapted to thermal integration.

· file thermal messages.hh

Define the class ThermalMessages, the class that specifies the message IDs used in the model.

• file thermal_model_rider.hh

Defining the thermal functionality.

• file thermal_params.hh

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

• file thermal_facet_rider.cc

ThermalFacetRider interaction model.

file thermal_integrable_object.cc

Encapsulates an integrator for a single facet.

• file thermal_messages.cc

Implement the class ThermalMessages.

• file thermal_model_rider.cc

ThermalModelRider interaction model.

• file thermal_params.cc

Thermal Parameter definition.

Namespaces

jeod

Namespace jeod.

Macros

• #define PATH "utils/thermal_rider/"

6.3.1 Detailed Description

6.3.2 Macro Definition Documentation

6.3.2.1 PATH

```
#define PATH "utils/thermal_rider/"
```

Definition at line 37 of file thermal_messages.cc.

14 Module Documentation

Namespace Documentation

7.1 jeod Namespace Reference

Namespace jeod.

Data Structures

· class ThermalFacetRider

Defining the thermal characteristics of surface facets.

class ThermalIntegrableObject

Encapsulates a thermal integrator for a facet.

· class ThermalMessages

Specifying the message IDs used in the model.

• class ThermalModelRider

Defining the thermal functionality.

• class ThermalParams

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

7.1.1 Detailed Description

Namespace jeod.

Data Structure Documentation

8.1 jeod::ThermalFacetRider Class Reference

Defining the thermal characteristics of surface facets.

```
#include <thermal_facet_rider.hh>
```

Public Member Functions

• ThermalFacetRider ()

Constructor.

virtual ∼ThermalFacetRider ()

Destructor

• void initialize (double temperature, double surface_area)

Initialize the thermal aspects of the facet.

void accumulate_thermal_sources (void)

Collects together all surface and internal thermal sources that affect a facet.

• double integrate (void)

Runge-Kutta 4th order integration of the temperature variation.

Data Fields

• double d_temperature

Change in temperature.

· double power absorb

Rate at which energy is absorbed from the environment, vehicle, and surface.

double power_emit

Rate at which energy is thermally radiated from the facet.

double heat_capacity

Heat capacity of the facet.

• double rad_constant

Combination of variables that are held constant for any given facet.

• InteractionFacet * facet

Pointer back to facet that contains this thermal rider.

· bool active

Flag set to indicate whether the facet to which this rider is attached has a dynamic temperature variability.

double thermal_power_dump

Rate at which thermal energy is transferred to the facet from within the vehicle.

· double emissivity

Fraction of sigma- T^4 (potential for emissive radiation) that is actually emitted.

• ThermalIntegrableObject integrable_object

The encapsulation of a first order integrator which can optionally be used to integrate the temperature.

Static Public Attributes

static double cycle_time = 0.0

Time since the last temperature calculation for the particular model under consideration.

Static Protected Attributes

static const double stefan_boltzmann = 5.6704004E-08
 Stefan-Boltzmann constant.

Private Member Functions

- ThermalFacetRider & operator= (const ThermalFacetRider &rhs)
- ThermalFacetRider (const ThermalFacetRider &rhs)

Private Attributes

• double next_temperature

The predicted value of temperature at the next time-step.

• double dynamic_temperature

The dynamic value of the facet kinetic temperature.

Friends

- class InputProcessor
- void init_attrjeod__ThermalFacetRider ()

8.1.1 Detailed Description

Defining the thermal characteristics of surface facets.

Definition at line 83 of file thermal facet rider.hh.

8.1.2 Constructor & Destructor Documentation

8.1.2.1 ThermalFacetRider() [1/2]

Constructor.

Definition at line 60 of file thermal_facet_rider.cc.

References active, d_temperature, dynamic_temperature, emissivity, facet, heat_capacity, next_temperature, power_absorb, power_emit, rad_constant, and thermal_power_dump.

8.1.2.2 ∼ThermalFacetRider()

Destructor.

Definition at line 313 of file thermal_facet_rider.cc.

8.1.2.3 ThermalFacetRider() [2/2]

8.1.3 Member Function Documentation

8.1.3.1 accumulate_thermal_sources()

Collects together all surface and internal thermal sources that affect a facet.

 $Definition \ at \ line \ 82 \ of \ file \ thermal_facet_rider.cc.$

References power_absorb, power_emit, and thermal_power_dump.

8.1.3.2 initialize()

Initialize the thermal aspects of the facet.

Parameters

in	temperature	temperature of facet Units: K
in	surface_area	area of facet surface
		Units: M*M

Definition at line 138 of file thermal_facet_rider.cc.

References dynamic_temperature, emissivity, jeod::ThermalMessages::incomplete_setup_error, jeod::Thermal IntegrableObject::initialize(), integrable_object, next_temperature, rad_constant, and stefan_boltzmann.

8.1.3.3 integrate()

Runge-Kutta 4th order integration of the temperature variation.

Returns

void

Definition at line 184 of file thermal_facet_rider.cc.

References active, cycle_time, d_temperature, dynamic_temperature, heat_capacity, jeod::ThermalMessages ::invalid_integration_operation, next_temperature, pow4, power_absorb, power_emit, and rad_constant.

8.1.3.4 operator=()

8.1.4 Friends And Related Function Documentation

8.1.4.1 init_attrjeod__ThermalFacetRider

```
void init_attrjeod__ThermalFacetRider ( ) [friend]
```

8.1.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 85 of file thermal_facet_rider.hh.

8.1.5 Field Documentation

8.1.5.1 active

```
bool jeod::ThermalFacetRider::active
```

Flag set to indicate whether the facet to which this rider is attached has a dynamic temperature variability.

```
trick_units(-)
```

Definition at line 142 of file thermal_facet_rider.hh.

Referenced by integrate(), and ThermalFacetRider().

8.1.5.2 cycle_time

```
double jeod::ThermalFacetRider::cycle_time = 0.0 [static]
```

Time since the last temperature calculation for the particular model under consideration.

trick_units(s)

Definition at line 95 of file thermal_facet_rider.hh.

Referenced by integrate(), and jeod::ThermalModelRider::update().

8.1.5.3 d_temperature

```
\verb|double jeod::ThermalFacetRider::d_temperature|\\
```

Change in temperature.

trick_units(-)

Definition at line 100 of file thermal_facet_rider.hh.

Referenced by integrate(), and ThermalFacetRider().

8.1.5.4 dynamic_temperature

```
double jeod::ThermalFacetRider::dynamic_temperature [private]
```

The dynamic value of the facet kinetic temperature.

THIS VALUE IS USED ONLY BY THE THERMAL INTEGRATOR, AND SHOULD NOT BE SET EXTERNALLY. ↔ trick_units(K)

Definition at line 185 of file thermal_facet_rider.hh.

Referenced by initialize(), integrate(), and ThermalFacetRider().

8.1.5.5 emissivity

```
double jeod::ThermalFacetRider::emissivity
```

Fraction of sigma-T⁴ (potential for emissive radiation) that is actually emitted.

trick_units(-)

Definition at line 158 of file thermal_facet_rider.hh.

Referenced by initialize(), and ThermalFacetRider().

8.1.5.6 facet

```
InteractionFacet* jeod::ThermalFacetRider::facet
```

Pointer back to facet that contains this thermal rider.

trick_units(-)

Definition at line 134 of file thermal facet rider.hh.

Referenced by ThermalFacetRider().

8.1.5.7 heat_capacity

```
double jeod::ThermalFacetRider::heat_capacity
```

Heat capacity of the facet.

trick_units(-)

Definition at line 120 of file thermal_facet_rider.hh.

Referenced by jeod::ThermalIntegrableObject::compute_temp_dot(), integrate(), and ThermalFacetRider().

8.1.5.8 integrable_object

```
ThermalIntegrableObject jeod::ThermalFacetRider::integrable_object
```

The encapsulation of a first order integrator which can optionally be used to integrate the temperature.

trick units(-)

Definition at line 164 of file thermal facet rider.hh.

Referenced by initialize().

8.1.5.9 next_temperature

```
double jeod::ThermalFacetRider::next_temperature [private]
```

The predicted value of temperature at the next time-step.

THIS VALUE IS USED ONLY BY THE THERMAL INTEGRATOR, AND SHOULD NOT BE SET EXTERNALLY. ← trick_units(K)

Definition at line 179 of file thermal_facet_rider.hh.

Referenced by initialize(), integrate(), and ThermalFacetRider().

8.1.5.10 power absorb

```
double jeod::ThermalFacetRider::power_absorb
```

Rate at which energy is absorbed from the environment, vehicle, and surface.

trick_units(-)

Definition at line 106 of file thermal_facet_rider.hh.

Referenced by accumulate_thermal_sources(), jeod::ThermalIntegrableObject::compute_temp_dot(), jeod::

ThermalIntegrableObject::integrate(), integrate(), and ThermalFacetRider().

8.1.5.11 power_emit

```
double jeod::ThermalFacetRider::power_emit
```

Rate at which energy is thermally radiated from the facet.

trick_units(-)

Definition at line 111 of file thermal_facet_rider.hh.

Referenced by accumulate_thermal_sources(), jeod::ThermalIntegrableObject::compute_temp_dot(), integrate(), and ThermalFacetRider().

8.1.5.12 rad_constant

```
double jeod::ThermalFacetRider::rad_constant
```

Combination of variables that are held constant for any given facet.

```
trick_units(-)
```

Definition at line 129 of file thermal_facet_rider.hh.

Referenced by jeod::ThermalIntegrableObject::compute_temp_dot(), initialize(), jeod::ThermalIntegrableObject::integrate(), integrate(), and ThermalFacetRider().

8.1.5.13 stefan_boltzmann

```
const double jeod::ThermalFacetRider::stefan_boltzmann = 5.6704004E-08 [static], [protected]
```

Stefan-Boltzmann constant.

```
trick_io(*o) trick_units(-)
```

Definition at line 171 of file thermal_facet_rider.hh.

Referenced by initialize().

8.1.5.14 thermal_power_dump

```
double jeod::ThermalFacetRider::thermal_power_dump
```

Rate at which thermal energy is transfered to the facet from within the vehicle.

trick_units(-)

Definition at line 148 of file thermal_facet_rider.hh.

Referenced by accumulate_thermal_sources(), and ThermalFacetRider().

The documentation for this class was generated from the following files:


- · thermal_facet_rider.hh
- thermal_facet_rider.cc

8.2 jeod::ThermalIntegrableObject Class Reference

Encapsulates a thermal integrator for a facet.

```
#include <thermal_integrable_object.hh>
```

Inheritance diagram for jeod::ThermalIntegrableObject:



Public Member Functions

• ThermalIntegrableObject ()

ThermalIntegrableObject default constructor.

virtual ∼ThermalIntegrableObject ()

ThermalIntegrableObject destructor.

• void initialize (double temperature, ThermalFacetRider &associated_rider)

Initialize temperature and cache a pointer to the ThermalFacetRider.

virtual void create_integrators (const er7_utils::IntegratorConstructor &generator, er7_utils::Integration
 — Controls &controls, const er7_utils::TimeInterface &time_if)

Create the first order integrator for this IntegrableObject.

• virtual void destroy_integrators ()

Destroy integrators for this IntegrableObject.

• virtual void reset_integrators ()

Reset the integrator.

• virtual er7_utils::IntegratorResult integrate (double dyn_dt, unsigned int target_stage)

Integrate the thermal state.

void compute_temp_dot ()

Compute emitted power and the time derivative of temperature.

• double get_temp ()

Get the temperature.

double get_temp_dot ()

Get the temperature time derivative.

Data Fields

bool active

If true, this IntegrableObject will integrate temperature.

Private Member Functions

- ThermalIntegrableObject & operator= (const ThermalIntegrableObject &rhs)
- ThermalIntegrableObject (const ThermalIntegrableObject &rhs)

Private Attributes

· RestartableScalarFirstOrderODEIntegrator integrator

Integrates temperature on one facet.

• ThermalFacetRider * rider

Cached pointer to the associated ThermalFacetRider.

· double temp

Temperature of the facet.

double temp_dot

Time derivative of temperature.

double t_pow4

Fourth power of current temperature.

Friends

- · class InputProcessor
- void init_attrjeod__ThermalIntegrableObject ()

8.2.1 Detailed Description

Encapsulates a thermal integrator for a facet.

Definition at line 87 of file thermal_integrable_object.hh.

8.2.2 Constructor & Destructor Documentation

```
8.2.2.1 ThermalIntegrableObject() [1/2]
```

```
{\tt jeod::} Thermal Integrable Object:: Thermal Integrable Object \ (\ )
```

ThermalIntegrableObject default constructor.

Definition at line 47 of file thermal_integrable_object.cc.

References integrator.

8.2.2.2 \sim ThermalIntegrableObject()

```
jeod::ThermalIntegrableObject::~ThermalIntegrableObject ( ) [virtual]
```

ThermalIntegrableObject destructor.

Definition at line 60 of file thermal_integrable_object.cc.

References destroy_integrators(), and integrator.

8.2.2.3 ThermalIntegrableObject() [2/2]

8.2.3 Member Function Documentation

8.2.3.1 compute_temp_dot()

Compute emitted power and the time derivative of temperature.

Definition at line 163 of file thermal_integrable_object.cc.

References jeod::ThermalFacetRider::heat_capacity, jeod::ThermalFacetRider::power_absorb, jeod::ThermalFacetRider::power_emit, jeod::ThermalFacetRider::rad_constant, rider, t_pow4, and temp_dot.

8.2.3.2 create_integrators()

Create the first order integrator for this IntegrableObject.

Parameters

generator	Integrator constructor that creates the integrator.	
controls	Integration controls that mediates the integrations.	
time_if	Unused.	

Definition at line 74 of file thermal_integrable_object.cc.

References integrator.

8.2.3.3 destroy_integrators()

Destroy integrators for this IntegrableObject.

Definition at line 87 of file thermal_integrable_object.cc.

Referenced by ~ThermalIntegrableObject().

```
8.2.3.4 get_temp()
```

```
double jeod::ThermalIntegrableObject::get_temp ( ) [inline]
```

Get the temperature.

Returns

Facet temperature.

Definition at line 125 of file thermal_integrable_object.hh.

References temp.

```
8.2.3.5 get_temp_dot()
```

```
double jeod::ThermalIntegrableObject::get_temp_dot ( ) [inline]
```

Get the temperature time derivative.

Returns

Facet temperature time derivative.

Definition at line 134 of file thermal_integrable_object.hh.

References temp_dot.

8.2.3.6 initialize()

Initialize temperature and cache a pointer to the ThermalFacetRider.

Parameters

temperature	- initial temperature
associated_rider	- the associated ThermalFacetRider

Definition at line 148 of file thermal_integrable_object.cc.

References rider, t_pow4, and temp.

Referenced by jeod::ThermalFacetRider::initialize().

8.2.3.7 integrate()

```
er7_utils::IntegratorResult jeod::ThermalIntegrableObject::integrate ( double \ dyn\_dt, unsigned \ int \ target\_stage \ ) \quad [virtual]
```

Integrate the thermal state.

Parameters

in	dyn_dt	Dynamic time step, in dynamic time seconds.
in	target_stage	The stage of the integration process that the integrator should try to attain.

Returns

The status (time advance, pass/fail status) of the integration.

Definition at line 113 of file thermal_integrable_object.cc.

References integrator, jeod::ThermalMessages::invalid_integration_operation, jeod::ThermalFacetRider::power_
absorb, jeod::ThermalFacetRider::rad_constant, rider, t_pow4, temp, and temp_dot.

8.2.3.8 operator=()

8.2.3.9 reset_integrators()

Reset the integrator.

Definition at line 98 of file thermal_integrable_object.cc.

References integrator.

8.2.4 Friends And Related Function Documentation

8.2.4.1 init_attrjeod__ThermalIntegrableObject

```
void init_attrjeod__ThermalIntegrableObject ( ) [friend]
```

8.2.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 89 of file thermal_integrable_object.hh.

8.2.5 Field Documentation

8.2.5.1 active

bool jeod::ThermalIntegrableObject::active

If true, this IntegrableObject will integrate temperature.

trick_units(-)

Definition at line 145 of file thermal_integrable_object.hh.

8.2.5.2 integrator

RestartableScalarFirstOrderODEIntegrator jeod::ThermalIntegrableObject::integrator [private]

Integrates temperature on one facet.

trick_units(-)

Definition at line 153 of file thermal_integrable_object.hh.

Referenced by create_integrators(), integrate(), reset_integrators(), ThermalIntegrableObject(), and \sim Thermal \leftrightarrow IntegrableObject().

8.2.5.3 rider

```
ThermalFacetRider* jeod::ThermalIntegrableObject::rider [private]
```

Cached pointer to the associated ThermalFacetRider.

trick units(-)

Definition at line 158 of file thermal integrable object.hh.

Referenced by compute_temp_dot(), initialize(), and integrate().

8.2.5.4 t_pow4

```
double jeod::ThermalIntegrableObject::t_pow4 [private]
```

Fourth power of current temperature.

trick_units(K*K*K*K)

Definition at line 173 of file thermal_integrable_object.hh.

Referenced by compute_temp_dot(), initialize(), and integrate().

8.2.5.5 temp

```
double jeod::ThermalIntegrableObject::temp [private]
```

Temperature of the facet.

trick_units(K)

Definition at line 163 of file thermal_integrable_object.hh.

Referenced by get_temp(), initialize(), and integrate().

8.2.5.6 temp_dot

```
double jeod::ThermalIntegrableObject::temp_dot [private]
```

Time derivative of temperature.

trick_units(K/s)

Definition at line 168 of file thermal integrable object.hh.

Referenced by compute_temp_dot(), get_temp_dot(), and integrate().

The documentation for this class was generated from the following files:

- thermal_integrable_object.hh
- thermal_integrable_object.cc

8.3 jeod::ThermalMessages Class Reference

Specifying the message IDs used in the model.

```
#include <thermal_messages.hh>
```

Static Public Attributes

- static char const * incomplete_setup_error
 - Generic error; the model was not set up correctly.
- static char const * invalid_integration_operation

The integration is invalid, usually because the integration step is too large.

Private Member Functions

- ThermalMessages (void)
- ThermalMessages (const ThermalMessages &)
- ThermalMessages & operator= (const ThermalMessages &)

Friends

- class InputProcessor
- void init_attrjeod__ThermalMessages ()

8.3.1 Detailed Description

Specifying the message IDs used in the model.

Definition at line 81 of file thermal_messages.hh.

8.3.2 Constructor & Destructor Documentation

```
8.3.2.1 ThermalMessages() [1/2]
```

8.3.2.2 ThermalMessages() [2/2]

8.3.3 Member Function Documentation

```
8.3.3.1 operator=()
```

8.3.4 Friends And Related Function Documentation

8.3.4.1 init_attrjeod__ThermalMessages

```
void init_attrjeod__ThermalMessages ( ) [friend]
```

8.3.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 84 of file thermal_messages.hh.

8.3.5 Field Documentation

8.3.5.1 incomplete_setup_error

```
char const * jeod::ThermalMessages::incomplete_setup_error [static]
```

Initial value:

```
"utils/thermal_rider/" "incomplete_setup_error"
```

Generic error; the model was not set up correctly.

trick_units(-)

Definition at line 93 of file thermal_messages.hh.

 $Referenced\ by\ jeod:: Thermal Facet Rider:: initialize ().$

8.3.5.2 invalid_integration_operation

```
char const * jeod::ThermalMessages::invalid_integration_operation [static]
```

Initial value:

```
"utils/thermal_rider/" "invalid_integration_operation"
```

The integration is invalid, usually because the integration step is too large.

trick_units(-)

Definition at line 100 of file thermal_messages.hh.

Referenced by jeod::ThermalIntegrableObject::integrate(), and jeod::ThermalFacetRider::integrate().

The documentation for this class was generated from the following files:

- · thermal_messages.hh
- thermal_messages.cc

8.4 jeod::ThermalModelRider Class Reference

Defining the thermal functionality.

```
#include <thermal_model_rider.hh>
```

Public Member Functions

• ThermalModelRider ()

Constructor.

• virtual \sim ThermalModelRider ()

Destructor.

• void update (InteractionSurface *surface_ptr)

update the thermal aspects of all facets

Data Fields

· bool active

Flag to allow thermal variation of facets.

• bool include_internal_thermal_effects

Flag to include facet-to-facet conduction, and vehicle-to-facet thermal sources and sinks.

Private Member Functions

- ThermalModelRider & operator= (const ThermalModelRider &rhs)
- ThermalModelRider (const ThermalModelRider &rhs)

Friends

- · class InputProcessor
- void init_attrjeod__ThermalModelRider ()

8.4.1 Detailed Description

Defining the thermal functionality.

Definition at line 84 of file thermal_model_rider.hh.

8.4.2 Constructor & Destructor Documentation

8.4.2.1 ThermalModelRider() [1/2]

Constructor.

Definition at line 53 of file thermal_model_rider.cc.

References active, and include_internal_thermal_effects.

8.4.2.2 ~ThermalModelRider()

```
\label{local_continuous} {\tt jeod::ThermalModelRider::\sim} {\tt ThermalModelRider:(} \\ {\tt void} \quad {\tt )} \quad [{\tt virtual}]
```

Destructor.

Definition at line 83 of file thermal_model_rider.cc.

8.4.2.3 ThermalModelRider() [2/2]

8.4.3 Member Function Documentation

8.4.3.1 operator=()

update the thermal aspects of all facets

Parameters

in surface_ptr	pointer the surface.
----------------	----------------------

Definition at line 65 of file thermal_model_rider.cc.

 $References\ active,\ jeod:: Thermal Facet Rider:: cycle_time,\ and\ include_internal_thermal_effects.$

8.4.4 Friends And Related Function Documentation

8.4.4.1 init_attrjeod__ThermalModelRider

```
void init_attrjeod__ThermalModelRider ( ) [friend]
```

8.4.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file thermal_model_rider.hh.

8.4.5 Field Documentation

8.4.5.1 active

bool jeod::ThermalModelRider::active

Flag to allow thermal variation of facets.

trick_units(-)

Definition at line 92 of file thermal_model_rider.hh.

Referenced by ThermalModelRider(), and update().

8.4.5.2 include_internal_thermal_effects

```
bool jeod::ThermalModelRider::include_internal_thermal_effects
```

Flag to include facet-to-facet conduction, and vehicle-to-facet thermal sources and sinks.

trick_units(-)

Definition at line 98 of file thermal model rider.hh.

Referenced by ThermalModelRider(), and update().

The documentation for this class was generated from the following files:

- · thermal model rider.hh
- thermal_model_rider.cc

8.5 jeod::ThermalParams Class Reference

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

```
#include <thermal_params.hh>
```

Public Member Functions

• ThermalParams ()

Constructor.

virtual ∼ThermalParams ()

Destructor.

Data Fields

double emissivity

Fraction of sigma- T^4 (potential for emissive thermal) that is actually emitted.

double heat_capacity_per_area

Heat Capacity per unit area of surface.

double thermal_power_dump

Rate at which thermal energy is dumped (positive) / extracted (negative) into a facet from within the vehicle.

Private Member Functions

- ThermalParams & operator= (const ThermalParams &rhs)
- ThermalParams (const ThermalParams &rhs)

Friends

- class InputProcessor
- void init_attrjeod__ThermalParams ()

8.5.1 Detailed Description

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

Definition at line 85 of file thermal_params.hh.

8.5.2 Constructor & Destructor Documentation

Constructor.

Definition at line 47 of file thermal_params.cc.

References emissivity, heat_capacity_per_area, and thermal_power_dump.

8.5.2.2 \sim ThermalParams()

Destructor.

Definition at line 58 of file thermal_params.cc.

8.5.2.3 ThermalParams() [2/2]

```
{\tt jeod::ThermalParams::ThermalParams \ (} \\ {\tt const \ ThermalParams \ \& \ rhs \ )} \quad [{\tt private}]
```

8.5.3 Member Function Documentation

8.5.3.1 operator=()

8.5.4 Friends And Related Function Documentation

8.5.4.1 init_attrjeod__ThermalParams

```
void init_attrjeod__ThermalParams ( ) [friend]
```

8.5.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file thermal_params.hh.

8.5.5 Field Documentation

8.5.5.1 emissivity

```
double jeod::ThermalParams::emissivity
```

Fraction of sigma-T⁴ (potential for emissive thermal) that is actually emitted.

trick units(-)

Definition at line 94 of file thermal_params.hh.

Referenced by ThermalParams().

8.5.5.2 heat_capacity_per_area

```
double jeod::ThermalParams::heat_capacity_per_area
```

Heat Capacity per unit area of surface.

trick_units(-)

Definition at line 99 of file thermal params.hh.

Referenced by ThermalParams().

8.5.5.3 thermal_power_dump

```
double jeod::ThermalParams::thermal_power_dump
```

Rate at which thermal energy is dumped (positive) / extracted (negative) into a facet from within the vehicle.

Used for radiators and the like.trick_units(-)

Definition at line 106 of file thermal_params.hh.

Referenced by ThermalParams().

The documentation for this class was generated from the following files:

- · thermal params.hh
- · thermal_params.cc

Chapter 9

File Documentation

9.1 class_declarations.hh File Reference

Forward declaration of classes defined in Thermal_rider model.

Namespaces

• jeod

Namespace jeod.

9.1.1 Detailed Description

Forward declaration of classes defined in Thermal_rider model.

9.2 thermal_facet_rider.cc File Reference

ThermalFacetRider interaction model.

```
#include <cstddef>
#include <cmath>
#include "utils/message/include/message_handler.hh"
#include "../include/thermal_facet_rider.hh"
#include "../include/thermal_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

42 File Documentation

Macros

#define pow4(x) pow4_temp = (x) * (x), pow4_temp *= pow4_temp

9.2.1 Detailed Description

ThermalFacetRider interaction model.

9.2.2 Macro Definition Documentation

9.2.2.1 pow4

```
#define pow4(  x \text{ ) pow4\_temp = (x) * (x), pow4\_temp *= pow4\_temp}
```

Referenced by jeod::ThermalFacetRider::integrate().

9.3 thermal_facet_rider.hh File Reference

Defining the thermal characteristics of surface facets.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "thermal_integrable_object.hh"
```

Data Structures

· class jeod::ThermalFacetRider

Defining the thermal characteristics of surface facets.

Namespaces

• jeod

Namespace jeod.

9.3.1 Detailed Description

Defining the thermal characteristics of surface facets.

9.4 thermal_integrable_object.cc File Reference

Encapsulates an integrator for a single facet.

```
#include <cmath>
#include "../include/thermal_facet_rider.hh"
#include "../include/thermal_integrable_object.hh"
#include "../include/thermal_messages.hh"
```

Namespaces

jeod

Namespace jeod.

9.4.1 Detailed Description

Encapsulates an integrator for a single facet.

9.5 thermal_integrable_object.hh File Reference

Define an IntegrableObject class adapted to thermal integration.

```
#include "er7_utils/integration/core/include/integrable_object.hh"
#include "er7_utils/integration/core/include/integrator_result.hh"
#include "utils/integration/include/restartable_state_integrator.hh"
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::ThermalIntegrableObject

Encapsulates a thermal integrator for a facet.

Namespaces

· jeod

Namespace jeod.

9.5.1 Detailed Description

Define an IntegrableObject class adapted to thermal integration.

44 File Documentation

9.6 thermal_messages.cc File Reference

Implement the class ThermalMessages.

```
#include "../include/thermal_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

Macros

• #define PATH "utils/thermal_rider/"

9.6.1 Detailed Description

Implement the class ThermalMessages.

9.7 thermal_messages.hh File Reference

Define the class ThermalMessages, the class that specifies the message IDs used in the model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::ThermalMessages

Specifying the message IDs used in the model.

Namespaces

· jeod

Namespace jeod.

9.7.1 Detailed Description

Define the class ThermalMessages, the class that specifies the message IDs used in the model.

9.8 thermal_model_rider.cc File Reference

ThermalModelRider interaction model.

```
#include <cmath>
#include "../include/thermal_model_rider.hh"
#include "utils/surface_model/include/interaction_surface.hh"
#include "../include/thermal_facet_rider.hh"
```

Namespaces

· jeod

Namespace jeod.

9.8.1 Detailed Description

ThermalModelRider interaction model.

9.9 thermal_model_rider.hh File Reference

Defining the thermal functionality.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

class jeod::ThermalModelRider
 Defining the thermal functionality.

Namespaces

• jeod

Namespace jeod.

9.9.1 Detailed Description

Defining the thermal functionality.

9.10 thermal_params.cc File Reference

Thermal Parameter definition.

```
#include "../include/thermal_params.hh"
#include "utils/surface_model/include/interaction_surface.hh"
```

46 File Documentation

Namespaces

· jeod

Namespace jeod.

9.10.1 Detailed Description

Thermal Parameter definition.

9.11 thermal_params.hh File Reference

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

class jeod::ThermalParams

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

Namespaces

• jeod

Namespace jeod.

9.11.1 Detailed Description

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

Index

~ThermalFacetRider	jeod::ThermalMessages, 33
jeod::ThermalFacetRider, 19	init_attrjeodThermalFacetRider
~ThermalIntegrableObject	jeod::ThermalFacetRider, 20
jeod::ThermalIntegrableObject, 26	init_attrjeodThermalIntegrableObject
~ThermalModelRider	jeod::ThermalIntegrableObject, 30
jeod::ThermalModelRider, 35	init_attrjeodThermalMessages
~ThermalParams	jeod::ThermalMessages, 33
jeod::ThermalParams, 39	init_attrjeodThermalModelRider
joodmeman aramo, oo	jeod::ThermalModelRider, 37
accumulate_thermal_sources	init_attrjeodThermalParams
jeod::ThermalFacetRider, 19	jeod::ThermalParams, 40
active	initialize
jeod::ThermalFacetRider, 21	jeod::ThermalFacetRider, 19
jeod::ThermalIntegrableObject, 30	jeod::ThermalIntegrableObject, 28
jeod::ThermalModelRider, 37	InputProcessor
•	jeod::ThermalFacetRider, 20
class_declarations.hh, 41	jeod::ThermalIntegrableObject, 30
compute_temp_dot	jeod::ThermalMessages, 33
jeod::ThermalIntegrableObject, 27	jeod::ThermalModelRider, 37
create_integrators	jeod::ThermalParams, 40
jeod::ThermalIntegrableObject, 27	integrable object
cycle_time	jeod::ThermalFacetRider, 22
jeod::ThermalFacetRider, 21	integrate
	jeod::ThermalFacetRider, 20
d_temperature	jeod::ThermalIntegrableObject, 29
jeod::ThermalFacetRider, 21	integrator
destroy_integrators	jeod::ThermalIntegrableObject, 30
jeod::ThermalIntegrableObject, 27	Interactions, 12
dynamic_temperature	invalid_integration_operation
jeod::ThermalFacetRider, 21	jeod::ThermalMessages, 33
emissivity	
jeod::ThermalFacetRider, 22	jeod, 15
jeod::ThermalParams, 40	jeod::ThermalFacetRider, 17
jeoumemararams, 40	\sim ThermalFacetRider, 19
facet	accumulate_thermal_sources, 19
jeod::ThermalFacetRider, 22	active, 21
jooda a.c, <u></u>	cycle_time, 21
get_temp	d_temperature, 21
jeod::ThermalIntegrableObject, 28	dynamic_temperature, 21
get_temp_dot	emissivity, 22
jeod::ThermalIntegrableObject, 28	facet, 22
	heat_capacity, 22
heat_capacity	init_attrjeodThermalFacetRider, 20
jeod::ThermalFacetRider, 22	initialize, 19
heat_capacity_per_area	InputProcessor, 20
jeod::ThermalParams, 40	integrable_object, 22
	integrate, 20
include_internal_thermal_effects	next_temperature, 23
jeod::ThermalModelRider, 37	operator=, 20
incomplete_setup_error	power_absorb, 23

48 INDEX

power_emit, 23	jeod::ThermalMessages, 33
rad_constant, 23	jeod::ThermalModelRider, 35
stefan_boltzmann, 24	jeod::ThermalParams, 39
thermal_power_dump, 24	
ThermalFacetRider, 18, 19	PATH
jeod::ThermalIntegrableObject, 25	ThermalRider, 13
~ThermalIntegrableObject, 26	pow4
active, 30	thermal_facet_rider.cc, 42
compute_temp_dot, 27	power_absorb
create_integrators, 27	jeod::ThermalFacetRider, 23
destroy_integrators, 27	power_emit
get_temp, 28	jeod::ThermalFacetRider, 23
get_temp_dot, 28	jooda doon noo., 20
	rad constant
init_attrjeodThermalIntegrableObject, 30	jeod::ThermalFacetRider, 23
initialize, 28	reset_integrators
InputProcessor, 30	jeod::ThermalIntegrableObject, 29
integrate, 29	rider
integrator, 30	jeod::ThermalIntegrableObject, 30
operator=, 29	jeddmeimaimtegrabieObject, 30
reset_integrators, 29	stefan_boltzmann
rider, 30	jeod::ThermalFacetRider, 24
t_pow4, 31	jeodmerman acetrider, 24
temp, 31	t_pow4
temp dot, 31	jeod::ThermalIntegrableObject, 31
ThermalIntegrableObject, 26	temp
jeod::ThermalMessages, 32	jeod::ThermalIntegrableObject, 31
incomplete_setup_error, 33	
init_attrjeodThermalMessages, 33	temp_dot
InputProcessor, 33	jeod::ThermalIntegrableObject, 31
invalid_integration_operation, 33	thermal_facet_rider.cc, 41
operator=, 33	pow4, 42
ThermalMessages, 32	thermal_facet_rider.hh, 42
	thermal_integrable_object.cc, 43
jeod::ThermalModelRider, 34	thermal_integrable_object.hh, 43
~ThermalModelRider, 35	thermal_messages.cc, 44
active, 37	thermal_messages.hh, 44
include_internal_thermal_effects, 37	thermal_model_rider.cc, 45
init_attrjeodThermalModelRider, 37	thermal_model_rider.hh, 45
InputProcessor, 37	thermal_params.cc, 45
operator=, 35	thermal_params.hh, 46
ThermalModelRider, 35	thermal_power_dump
update, 36	jeod::ThermalFacetRider, 24
jeod::ThermalParams, 38	jeod::ThermalParams, 40
\sim ThermalParams, 39	ThermalFacetRider
emissivity, 40	jeod::ThermalFacetRider, 18, 19
heat_capacity_per_area, 40	ThermalIntegrableObject
init_attrjeodThermalParams, 40	jeod::ThermalIntegrableObject, 26
InputProcessor, 40	ThermalMessages
operator=, 39	jeod::ThermalMessages, 32
thermal_power_dump, 40	ThermalModelRider
ThermalParams, 39	jeod::ThermalModelRider, 35
	ThermalParams
Models, 11	jeod::ThermalParams, 39
	ThermalRider, 13
next_temperature	
jeod::ThermalFacetRider, 23	PATH, 13
	update
operator=	jeod::ThermalModelRider, 36
jeod::ThermalFacetRider, 20	jeod mermanvioden tider, 30
ieod::ThermalIntegrableObject, 29	