
Configuration routage dynamique (RIP)

network [adresse ip du sous réseau connecté au routeur]



```
R2>en
                                                         R2#conf t
R1>en
R1#conf t
                                                        R2(config)#interface fa0/0
R1(config)#interface fa0/0
                                                        R2(config-if)#ip address 192.168.2.254 255.255.255.0
R1(config-if) #ip address 192.168.1.254 255.255.255.0
                                                        R2(config-if) #no shutdown
R1(config-if) #no shutdown
                                                        R2(config-if)#exit
R1(config-if)#exit
                                                        R2(config)#interface fa0/1
R1(config)#interface fa0/1
                                                        R2(config-if)#ip address 11.0.0.2 255.255.255.0
R1(config-if)#ip address 10.0.0.1 255.255.255.0
                                                        R2(config-if)#no shutdown
R1(config-if) #no shutdown
                                                        R2(config-if)#exit
R1(config-if)#exit
                                                        R2(config)#interface Ethernet0/0/0
Rl(config) #router rip
                                                        R2(config-if)#ip address 10.0.0.2 255.255.255.0
R1(config-router) #version 2
                                                        R2(config-if)#no shutdown
R1(config-router) #network 192.168.1.0
                                                        R2(config-if)#exit
R1(config-router) #network 10.0.0.0
                                                        R2(config) #router rip
Rl(config-router) #exit
                                                        R2(config-router) #version 2
R1(config)#exit
                                                        R2(config-router) #network 10.0.0.0
Rl#copy run start
                                                        R2(config-router) #network 192.168.2.0
                                                        R2(config-router) #network 11.0.0.0
                                                        R2(config-router)#exit
                                                        R2(config)#exit
                                                        R2#copy run start
                          R3>en
                          R3#conf t
                          R3(config)#interface fa0/1
                         R3(config-if)#ip address 11.0.0.3 255.255.255.0
```

```
R3#conf t
R3(config)#interface fa0/1
R3(config-if)#ip address 11.0.0.3 255.255.255.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#interface fa0/0
R3(config-if)#ip address 192.168.3.254 255.255.255.0
R3(config-if)#no shutdown
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config-if)#exit
R3(config-router)#version 2
R3(config-router)#version 2
R3(config-router)#network 192.168.3.0
R3(config-router)#network 11.0.0.0
R3(config-router)#exit
R3(config)#exit
R3(config)#exit
```