HelloWorld2

Generated by Doxygen 1.8.6

Tue Sep 29 2015 15:56:13

Contents

1 Index Page **1**

1.1 General Description . . . 1

1.2 Hardware . . . 1

1.2.1 Hardware Variants . . . 1

2 File Index **3**

2.1 File List . . . 3

3 File Documentation **5**

3.1 HelloWorld2.c File Reference . . . 5

3.1.1 Detailed Description . . . 6

3.1.2 Macro Definition Documentation . . . 6

3.1.2.1 _LED200 . . . 6

3.1.2.2 EXIT_FAILURE . . . 6

3.1.2.3 EXIT_SUCCESS . . . 6

3.1.3 Function Documentation . . . 6

3.1.3.1 _FOSC . . . 6

3.1.3.2 _FOSCSEL . . . 6

3.1.3.3 delay_ms . . . 6

3.1.3.4 main . . . 7

3.2 readme.c File Reference . . . 7

Index **8**

Chapter 1

Index Page

1.1 General Description

The purpose of this software is getting started quickly with a basic functionality (blinking LED).

1.2 Hardware

The software has been designed for the EDA dsPIC33-board. Documentation is available on https://eda-wiki.eda.htw-aalen.de/studi/PIClab/ExperimentierBoardPIC24dsPIC33

1.2.1 Hardware Variants

Although beeing designed for the dsPIC33 variant, the software should also run on a board populated with the PIC24H-Controller. This has not been tested.

Chapter 2

File Index

2.1 File List

Here is a list of all files with brief descriptions:

HelloWorld2.c
Getting started with a simple program (blinking LED) 5
readme.c 7

Chapter 3


File Documentation

3.1 HelloWorld2.c File Reference

Getting started with a simple program (blinking LED)

```
#include <xc.h>
#include <stdint.h>
```

Include dependency graph for HelloWorld2.c:



Macros

- #define EXIT_SUCCESS 0
- #define EXIT_FAILURE 1
- #define _LED200 LATBbits.LATB8

Functions

- _FOSCSEL (FNOSC_FRC)
- _FOSC (POSCMD_NONE)
- void delay_ms (uint16_t u16milliseconds)

  Provides u16milliseconds delay.
- int main ()

  Toggles LED200 with 1 Hz, 1:1 duty cycle.

3.1.1 Detailed Description

Getting started with a simple program (blinking LED)

Author

JS

Date

26.08.2015, 12:43

Definition in file HelloWorld2.c.

3.1.2 Macro Definition Documentation

3.1.2.1 #define _LED200 LATBbits.LATB8

Definition at line 52 of file HelloWorld2.c.

3.1.2.2 #define EXIT_FAILURE 1

Definition at line 49 of file HelloWorld2.c.

3.1.2.3 #define EXIT_SUCCESS 0

Definition at line 48 of file HelloWorld2.c.

3.1.3 Function Documentation

3.1.3.1 _FOSC (POSCMD_NONE)

3.1.3.2 _FOSCSEL (FNOSC_FRC)

3.1.3.3 void delay_ms (uint16_t *u16milliseconds*)

Provides u16milliseconds delay.

Parameters

u16milliseconds	Delay in milliseconds

u16milliseconds=0 causes 65536 ms delay

Precondition


7.37 MHz (Internal Fast RC), e. g.:
_FOSCSEL(FNOSC_FRC); //Initial Oscillator: Internal Fast RC
_FOSC(POSCMD_NONE); //Primary Oscillator disabled (quartz not used)
s. 7.37 MHz DS70216C-page 39-19

Attention

Code has to be changed if a different oscillator frequency is used.

Definition at line 76 of file HelloWorld2.c.

Here is the caller graph for this function:




3.1.3.4 int main ( )

Toggles LED200 with 1 Hz, 1:1 duty cycle.

Hello World (Blinking LED)

Definition at line 98 of file HelloWorld2.c.

Here is the call graph for this function:



3.2 readme.c File Reference

Index

_FOSC
    HelloWorld2.c, 6
_FOSCSEL
    HelloWorld2.c, 6
_LED200
    HelloWorld2.c, 6

delay_ms
    HelloWorld2.c, 6

EXIT_FAILURE
    HelloWorld2.c, 6
EXIT_SUCCESS
    HelloWorld2.c, 6

HelloWorld2.c, 5
    _FOSC, 6
    _FOSCSEL, 6
    _LED200, 6
    delay_ms, 6
    EXIT_FAILURE, 6
    EXIT_SUCCESS, 6
    main, 7

main
    HelloWorld2.c, 7

readme.c, 7