Staking Contract Address: 0xab6ef2576afcD7598E4DCfCA01215fEeA2a07C91 RTT Address for staking contract: 0x30ba2db859e2f998a82cb9485b0b288aea48651a


Airdrop Contract Address: 0x71E8ec88826A47f24631Dc2f01085e98b76685Da RTT Address for airdrop contract: 0x8ce9bd698cf17200918379d06d85c01c1f12f1ab

Note: Now RTT address for airdrop and RTT address for staking is different. It is temporary. Once these contracts pass your testing and when these contracts deploy on the mainnet, I will use the same address of RTT for staking and airdrop.


Note: RTT token has 18 decimals. So you should consider the decimals when enter the RTT amount. 10000000000000000000 = 1RTT

How to confirm your balance exactly?

- Go to the token address.
 When you test the airdrop, RTT address: 0x8ce9bd698cf17200918379d06d85c01c1f12f1ab
 When you test the staking, RTT address: 0x30ba2db859e2f998a82cb9485b0b288aea48651a
- 2. Click "Read Contract" button.



- 3. Go to the balanceOf function
- 4. Put your address in the address field
- 5. Click the "Query" button.
- 6. You can see your RTT balance.



Guide for airdrop:

dropTokens(No 2) function will send presetted RTT amount to all putted addresses. You can preset the airdrop amount.

Following below:

- 1. connect your metamask to the BSC testnet.
- 2. Go to the updateDropAmount function(No 8).



10000000000000000000 = 100RTT

3. go to the dropTokens function and put the addresses in the input field.

[0xDF465C98bB8dDC6eBb7F9c1086120FD01eEF70AD,

0x7656da7821e1eC8cA663995523037Ce00372a8d8]

Note: Your balance should be above 100*2 = 200RTT. You should check your balance before airdrop.




These two addresses will get the 100RTT tokens.

- 4. click the write button
- 5. confirm.


If the airdrop success, the 0xDF465C98bB8dDC6eBb7F9c1086120FD01eEF70AD address and 0x7656da7821e1eC8cA663995523037Ce00372a8d8 address will add 100RTT tokens.

Guide for staking:

- 1. Go to the RTT token address on the bscscan Rtt address: 0x30ba2db859e2f998a82cb9485b0b288aea48651a
- 2. Confirm your RTT balance
- 3. Approve your RTT tokens




- 4. Go to the staking contract on the bsc Staking address: 0xab6ef2576afcD7598E4DCfCA01215fEeA2a07C91
- 5. Call deposit function



6. Check your reward amount.



7. Call emergencyWithdraw function



8. Confirm your balance

Your balance will be initial balance+reward amount