Created with a trial version of Syncfusion PDF library or registered the wrong key in your application. Click here to obtain the valid key.

## 2D Barcodes

#### **QR Barcode**



Input Type :Eight Bit Binary

Encoded Data: Syncfusion Essential Studio Enterprise edition \$995

## **QR Barcode with logo**



Encoded Data: https://www.syncfusion.com

### **DataMatrix Barcode**



Symbol Type : Square

Encoded Data: 5575235 Win7 4GB 64bit 7Jun2010



Symbol Type: Rectangle

Encoded Data: TYPE 3523 - ETWS/N FE- SDFHW 06/08

## PDF417 Barcode



Encoded Data: https://www.syncfusion.com/

# 1D/Linear Barcodes



Type: Code39

Allowed Characters: 0-9, A-Z,a dash(-),a dot(.),\$,/,+,%, SPACE



Type: Code39Ext

Allowed Characters: 0-9 A-Z a-z



Type: Code 11

Allowed Characters : 0-9: a dash(-)



Type: Codabar

Allowed Characters : A,B,C,D,0-9,-\$,:,/,a dot(.),+



Type: Code32

Allowed Characters: 1 2 3 4 5 6 7 8 9 0



ABC 123456

Type: Code93

Allowed Characters: 1234567890ABCDEFGHIJKLMNOPQRS

T U V W X Y Z - . \$/+% SPACE



Type: Code93 Extended

Allowed Characters: All 128 ASCII characters



Type: Code128 A

Allowed Characters: NUL (0x00) SOH (0x01) STX (0x02) ETX (0x03) EOT (0x04) ENQ (0x05) ACK (0x06) BEL (0x07) BS (0x08) HT (0x09) LF (0x0A) VT (0x0B) FF (0x0C) CR (0x0D) SO (0x0E) SI (0x0F) DLE (0x10) DC1 (0x11) DC2 (0x12) DC3 (0x13) DC4 (0x14) NAK (0x15) SYN (0x16) ETB (0x17) CAN (0x18) EM (0x19) SUB (0x1A) ESC (0x1B) FS (0x1C) GS (0x1D) RS (0x1E) US (0x1F) SPACE (0x20) "!#\$ % & '()\*+,-./0123456789:;<=>? @ A BCDEFGHIJKLMNOPQRSTUVWXYZ[/]^\_



Type: Code128 B

Allowed Characters: SPACE (0x20) \* # \$ % & '() \* +, -./0123456789: ;<=>?@ABCDEFGHIJKLMNOPQRSTUVWXYZ[/]^\_`a b c d e f g h i j k l m n o p q r s t v w x y z { | } ~ DEL (•)



Type: Code128 C

Allowed Characters: 0 1 2 3 4 5 6 7 8 9



Created with Type: UPC-A

Allowed Characters: 0-9



Type: EAN-13

Allowed Characters: 0-9



Type: EAN-8

Allowed Characters: 0-9