




WORKSTATION PRO™ 17

New Virtual Machine Wizard

vmware
WORKSTATION
PRO™
17

Welcome to the New Virtual Machine Wizard

What type of configuration do you want?

☐ Typical (recommended)
Create a Workstation 17.5 or later virtual machine in a few easy steps.

☒ Custom (advanced)
Create a virtual machine with advanced options, such as a SCSI controller type, virtual disk type and compatibility with older VMware products.


Help


< Back

Next >

Cancel

Connect to a Remote Server






We're getting everything ready for you

in the virtual screen to
keystrokes

Easy Install is installing VMware Tools on Windows 10 x64.

press Ctrl+G.





Windows Setup

Installing Windows

Status

- ✓ Copying Windows files
 - Getting files ready for installation (41%)**
 - Installing features
 - Installing updates
 - Finishing up

1 Collecting information

2 Installing Windows

h the virtual screen to
keystrokes

Easy Install is installing Windows 10 x64.

press Ctrl+G.



Search



WORKSTATION PRO™ 17

New Virtual Machine Wizard

Specify Disk Capacity

How large do you want this disk to be?

Maximum disk size (GB):

60.0

Recommended size for Windows 10 x64: 60 GB

☐ Allocate all disk space now.

Allocating the full capacity can enhance performance but requires all of the physical disk space to be available right now. If you do not allocate all the space now, the virtual disk starts small and grows as you add data to it.

☐ Store virtual disk as a single file

☒ Split virtual disk into multiple files

Splitting the disk makes it easier to move the virtual machine to another computer but may reduce performance with very large disks.


Help

< Back

Next >

Cancel


Connect to a Remote Server



Snipping Tool

Screenshot copied to clipboard
Automatically saved to snipping tool

Markup



WORKSTATION PRO™ 17

New Virtual Machine Wizard

Select a Disk

Which disk do you want to use?

Disk



Create a new virtual disk

A virtual disk is composed of one or more files on the host file system, which will appear as a single hard disk to the guest operating system. Virtual disks can easily be copied or moved on the same host or between hosts.



Use an existing virtual disk

Choose this option to reuse a previously configured disk.



Use a physical disk (for advanced users)

Choose this option to give the virtual machine direct access to a local hard disk. Requires administrator privileges.

Help

< Back

Next >

Cancel



Connect to a
Remote Server

ware



Search



WORKSTATION PRO™ 17

New Virtual Machine Wizard



Network Type

What type of network do you want to add?

Network connection

- ☐ Use bridged networking
Give the guest operating system direct access to an external Ethernet network. The guest must have its own IP address on the external network.
- ☒ Use network address translation (NAT)
Give the guest operating system access to the host computer's dial-up or external Ethernet network connection using the host's IP address.
- ☐ Use host-only networking
Connect the guest operating system to a private virtual network on the host computer.
- ☐ Do not use a network connection

Help

< Back

Next >

Cancel



Connect to a
Remote Server



Screen
Auto

WORKSTATION PRO™ 17

New Virtual Machine Wizard

Memory for the Virtual Machine

How much memory would you like to use for this virtual machine?

Specify the amount of memory allocated to this virtual machine. The memory size must be a multiple of 4 MB.

Memory for this virtual machine: MB

128 GB -
64 GB -
32 GB -
16 GB -
8 GB -
4 GB -
2 GB -
1 GB -
512 MB -
256 MB -
128 MB -
64 MB -
32 MB -
16 MB -
8 MB -
4 MB -

Maximum recommended memory:
13.2 GB

Recommended memory:
2 GB

Guest OS recommended minimum:
2 GB

Help


< Back

Next >

Cancel



Connect to a Remote Server



WORKSTATION PRO™ 17

×

New Virtual Machine Wizard

×

Easy Install Information

This is used to install Windows 10 x64.

Windows product key

- - - -

Version of Windows to install

Windows 10 Pro

Personalize Windows

Full name: Admin

Password: (optional)

Confirm:

☐ Log on automatically (requires a password)

Help

< Back

Next >

Cancel

→
←

Connect to a Remote Server

ware