SN031 Stock transfers between warehouses

Item	Value
Scenario ID	SN031 (legacy business scenario, rewritten for QuroERP)
Module	MM (Purchasing & Inventory)
Screens · tasks	Warehouses MM-026, Stock Transfer MM-028, reports MM-017 · MM-022 · MM-037 · MM-029
Data	Demo data only (`--demo`, `Scripts/Demo/`), fictional names. Country `US`, currency USD
Dates	November 2026 (the steps give each date)
Languages	Check every screen once in en and once in ko (top-bar language switch)
Version	1 · 2026-11-10

1. Business background

Stock runs short in one place, so material moves between warehouses, and in the legacy system also between plants and business sites. A move changes where stock is, not its value. Material can also change its purpose (raw material sold as goods) or its condition (good stock turns defective).

2. Steps outside QuroERP and future scope

Legacy step	In this scenario
Transfer between warehouses (T01)	Stock Transfer (steps 2–5)
Transfer between plants (T11) and between business sites (T21)	QuroERP has no plants. A transfer between warehouses of different business places is **future scope**; the steps use warehouses of the default business place
Item-to-item transfer (raw material → goods) and good → defective	**Future scope**
Daily stock report, monthly voucher summary, financial statements	Inventory Statement and Stock Reconciliation reports; the rest **outside QuroERP**

3. Prerequisite data

No	Data	Where it comes from
P1	Warehouses: default (`MAIN`), `EAST` in use, `OLDYARD` not in use	Demo `0902`
P2	DEMO-PANEL-01 40 at 128.00; DEMO-CABLE-LOT 50 at 12.00 (lots L2611A 30, L2611B 20) in the default warehouse	Demo `0908`
P3	A fresh demo database	

4. Steps

Step	Screen (menu) · task	Action and input
1	Item Stock List · MM-017	Both items by warehouse
2	Stock Transfer · MM-028	2026-11-03, default → `EAST`. Lines: DEMO-PANEL-01 15, DEMO-CABLE-LOT 10 lot L2611B. Save
3	Stock Transfer · MM-028	New. To warehouse `OLDYARD`
4	Stock Transfer · MM-028	2026-11-05, `EAST` → default: DEMO-PANEL-01 20. Save (more than `EAST` holds)
5	Stock Transfer · MM-028	Change to 5. Save

Step	Screen (menu) · task	Action and input
6	Stock Transfer · MM-028	Open the transfer of step 2 and delete it
7	Item Stock List · MM-017, Inventory Statement · MM-022, Item Transactions · MM-037	November 2026
8	Stock Reconciliation report · MM-029	Run the check

5. Check list

☐	Step	Check point
☐	1	Default 40 / 50; `EAST` 0
☐	2	Number `TR` + `2611` + 10 digits. Each line shows the on-hand of the source warehouse. The lot item needs a lot
☐	2	Default: PANEL 25, CABLE 40 (L2611B 10). `EAST`: PANEL 15, CABLE 10 (L2611B). Costs 128.00 and 12.00 unchanged; out and in amounts equal
☐	3	`OLDYARD` (not in use) cannot be picked
☐	4	Refused or warned for negative stock in `EAST` under the stock mode (MM-BR-602)
☐	5	`EAST` PANEL 10, default PANEL 30
☐	6	Deleting is refused if it would make `EAST` negative (PANEL 10 < 15); otherwise both movements are reversed
☐	7	Totals unchanged: PANEL 40, CABLE 50; total stock value unchanged
☐	8	No differences between movements, on-hand and lot balances
☐	all	Each screen shows labels and messages in en and in ko after the language switch

SN031 창고 간 재고 이동

항목	값
시나리오 ID	SN031 (예전 업무 시나리오를 QuroERP에 맞게 다시 씀)
모듈	MM (구매·재고)
화면 · 태스크	창고 MM-026, 창고 간 재고 이동 MM-028, 리포트 MM-017 · MM-022 · MM-037 · MM-029
데이터	시연 데이터만 (`--demo`, `Scripts/Demo/`), 가상 이름. 국가 `US`, 통화 USD
날짜	2026년 11월 (단계마다 날짜를 적었다)
언어	화면마다 en 한 번, ko 한 번 확인한다 (상단바 언어 전환)
버전	1 · 2026-11-10

1. 업무 배경

한 곳에 재고가 모자라 창고 사이로, 예전 시스템에서는 공장·사업장 사이로도 자재를 옮긴다. 이동은 재고 위치만 바꾸고 금액은 바꾸지 않는다. 자재 용도가 바뀌거나(원자재를 상품으로 판매) 상태가 바뀌기도(양품이 불량) 한다.

2. QuroERP 밖 단계와 향후 범위

예전 단계	이 시나리오에서
창고 간 이동 (T01)	창고 간 재고 이동 (단계 2~5)
공장 간 이동 (T11), 사업장 간 이동 (T21)	QuroERP에는 공장이 없다. 다른 사업장 창고 사이 이동은 **향후 범위**. 단계는 기본 사업장 창고를 쓴다
품목 간 대체 (원자재 → 상품), 양품 → 불량	**향후 범위**
재고 일보, 월별 전표 집계, 재무제표	재고 수불부·재고 대사 점검 리포트. 나머지는 **QuroERP 밖 단계**

3. 사전 데이터

No	데이터	출처
P1	창고: 기본(`MAIN`), `EAST` 사용 중, `OLDYARD` 사용 안 함	시연 `0902`
P2	기본 창고 DEMO-PANEL-01 40개 128.00, DEMO-CABLE-LOT 50개 12.00 (로트 L2611A 30, L2611B 20)	시연 `0908`
P3	새 시연 DB	

4. 단계

단계	화면(메뉴) · 태스크	할 일과 입력
1	품목 재고 목록 · MM-017	두 품목 창고별
2	창고 간 재고 이동 · MM-028	2026-11-03, 기본 → `EAST`. 줄: DEMO-PANEL-01 15, DEMO-CABLE-LOT 10 로트 L2611B. 저장
3	창고 간 재고 이동 · MM-028	신규. 받는 창고 `OLDYARD`
4	창고 간 재고 이동 · MM-028	2026-11-05, `EAST` → 기본: DEMO-PANEL-01 20. 저장 (`EAST` 보유량보다 많음)
5	창고 간 재고 이동 · MM-028	5로 바꾼다. 저장
6	창고 간 재고 이동 · MM-028	단계 2 이동을 열어 삭제
7	품목 재고 목록 · MM-017, 재고 수불부 · MM-022, 품목 거래 내역 · MM-037	2026년 11월

단계	화면(메뉴) · 태스크	할 일과 입력
8	재고 대사 점검 리포트 · MM-029	점검 실행

5. 확인 목록

☐	단계	확인 포인트
☐	1	기본 40 / 50, `EAST` 0
☐	2	번호 `TR` + `2611` + 10자리. 줄마다 보내는 창고 현재고가 보인다. 로트 품목은 로트가 필요하다
☐	2	기본: PANEL 25, CABLE 40 (L2611B 10). `EAST`: PANEL 15, CABLE 10 (L2611B). 원가 128.00, 12.00 그대로, 출·입 금액이 같다
☐	3	`OLDYARD`(사용 안 함)는 고를 수 없다
☐	4	재고 모드에 따라 `EAST` 마이너스 재고로 막히거나 경고가 나온다 (MM-BR-602)
☐	5	`EAST` PANEL 10, 기본 PANEL 30
☐	6	`EAST`가 음수가 되면(PANEL 10 < 15) 삭제가 막힌다. 아니면 두 이동이 모두 되돌려진다
☐	7	합계 그대로: PANEL 40, CABLE 50, 재고 금액 합계 그대로
☐	8	이동·현재고·로트 잔고 사이에 차이가 없다
☐	전체	언어를 바꾸면 화면마다 라벨·메시지가 en, ko로 나온다