

Access Monitoring Tools



For supported software information, click <u>here</u>.


You can monitor the network using the ping, tcpdump, and traceroute commands, and you can run a speed test.

To access tools to monitor devices in the network:

- 1. In Director view:
 - a. Select the Configuration tab in the top menu bar.
 - b. Select Devices > Devices in the horizontal menu bar.
 - c. Select a device in the main pane. The view changes to Appliance view.
- 2. Select the Monitor tab in the top menu bar.
- 3. Select a provider in the left menu bar.
- 4. Select the Tools tab to access the following tools:
 - Ping
 - · Speed Test
 - Traceroute
 - Tcpdump

Ping

Click Ping. The following screen displays:




To ping a site:

- 1. Enter the host name/address.
- 2. Select the routing instance.
- 3. Select the source IP address.
- 4. Enter the packet size.
- 5. Enter the packet count.
- 6. Click Start.

Traceroute

Click Traceroute. The following screen displays:



To trace a route:

- 1. Enter the target host name or IP address.
- 2. Select the routing instance.
- 3. Select the source IP address.
- 4. Click Start.

Tcpdump

Click Tcpdump. The following screen displays:



To run tcpdump on an interface:

- 1. Select the interface.
- 2. Enter the type of filter to be applied.


https://docs.versa-networks.com/Management_and_Orchestration/Versa_Director/Monitoring_with_Versa_Director/Access_M... Updated: Thu, 24 Oct 2024 10:47:22 GMT

- 3. Enter the file name where you want the output to be saved.
- 4. Click Start.

Speed Test

You can set up a Versa Operating SystemTM (VOSTM) device to be a speed-test server and, from the local VOS device, you can run a speed test to test the link. For information about setting up a VOS device to be a speed-test server, see Troubleshoot Link Bandwidth Issues.

To run a speed test, click Speed Test. The following screen displays:



To test an interface's speed:

- 1. Enter the remote IP address.
- 2. Select the routing instance.
- 3. Select the interface.
- 4. Click Test Speed.

Supported Software Information

Releases 20.2 and later support all content described in this article.

Additional Information

Troubleshoot Link Bandwidth Issues