

JEFECORP

JefeCheck 
BETA

PLAY.PROCESS.SHARE

(WORK IN PROGRESS, FINAL VERSION TO BE RELEASED WITH SOFTWARE RELEASE)

Quick Reference

Table of Contents

TABLE OF CONTENTS	I
LOADING	2
How to Load an Image Sequence into track X	2
How to load only a certain range of an image sequence.....	2
How to Load a Sequence as a lower res proxy	2
How to Load Y number of sequences into several tracks.....	2
How to Load a sequence altering the gamma at load time (not reversible in real time)	3
How to load only a specific region of an image sequence.....	3
How to Load an image with 16 bit floating point precision	3
How to apply one or more LUTs to an image at Load time (not reversible in real time)	4
How to cancel loading of a sequence	4
How to start loading a sequence from a certain point in the timeline.....	4
PLAYBACK	5
Change the layout of the viewports.....	5
How to change what track is displayed on each viewport	5
How transform a viewport.....	5
How to change the aspect ratio of a viewport	5
How to see only certain channels on a viewport.....	6
How to control the playback.....	6
How to offset a track on the timeline.....	6
How to hold a specific frame on a track	6
How to unload a track.....	7
How to show or hide text information	7
How to show DPX Metadata on the viewport	7
PROCESSING	7
How to Load a JefeCheck FX	7
How to Load a LUT	7
How to apply one or more FXs to a viewport's FX stack.....	8
How to change the position of an FX in the FX stack.....	8
REMOTE SESSION.....	8
How to start a JefeCheck Remote Session Server.....	8
How to join a JefeCheck Remote Session Server	9
How to Chat in a Remote Session	9
How to use Remote Pointers in a Remote Session	10
How to Save a Chat from a Remote Session	10

Loading

How to Load an Image Sequence into track X

1. Open the Load Window (**Menu>File>Load Sequence or Ctrl+L**)
2. Click on the Browse button for track X 
3. Navigate the file systems to find your sequence and select any frame, click ok.
4. Click the Start Button in the Load Window 

How to load only a certain range of an image sequence

1. Follow steps 1 through 3 of How to Load an Image Sequence into track X on p2
2. Drag the **In and Out sliders** in the corresponding track in the Load Window 
 - a. In 1
 - b. Out 142
3. Click the Start Button in the Load Window 

How to Load a Sequence as a lower res proxy

1. Follow steps 1 through 3 of How to Load an Image Sequence into track X on p2.
2. Before pressing Start, select or type in a scale in the Scale Box for the sequence you are loading, select the filtering you want to apply when resizing the image (linear=fast, bilinear=better looking) 

100 % Filter Linear
3. Click the Start Button in the Load Window 

How to Load Y number of sequences into several tracks

1. Follow steps 1 through 3 of How to Load an Image Sequence into track X on p2 with up to four tracks (A, B, C and D).
2. Click the Start Button in the Load Window 

How to Load a sequence altering the gamma at load time (not reversible in real time)

1. Follow steps 1 through 3 of How to Load an Image Sequence into track X on p2
2. Change the value of the Gamma Box on track X in the Load Window by clicking and dragging on it with the left mouse button.
3. Click the Start Button in the Load Window



How to load only a specific region of an image sequence.

1. Follow steps 1 through 3 of How to Load an Image Sequence into track X.on on p2
2. Activate the Crop Checkbox for that track in the Load Window
3. Select the region you wish to load on the preview image shown in the Main Window. **Right Click and Drag to move** the Crop Region, **Shift+Right Click and Drag to resize** the Crop Region. You can zoom and pan with the left mouse button and mouse wheel.
4. Click the Start Button in the Load Window



How to Load an image with 16 bit floating point precision

Note that this will store images in 16 bit in memory, allowing greater precision when modifying 16 bit per component images with JefeCheck's FXs at the cost of double the memory usage. (you don't need to do this to simple load and playback 16bit per component images, **ONLY do it if you are experiencing problems when doing heavy processing**)

1. Follow steps 1 through 3 of How to Load an Image Sequence into track X.on on p2
2. Select **Half Float (x2)** from the Format Option Box in the Load Window.
3. Click the Start Button in the Load Window



How to apply one or more LUTs to an image at Load time (not reversible in real time)

1. Follow steps 1 through 3 of How to Load an Image Sequence into track X.on on p2
2. Select a LUT from the **LUT drop down menu** and click the **+** button to add the LUT to the LUT queue.
3. Add as many LUTs as you need to the LUT queue by repeating step 2. LUTs will be applied one after the other in the order they were added.
4. Remove any LUT from the queue by selecting it in the **Queued drop down menu** and clicking the **-** button.



5. Click the Start Button in the Load Window



How to cancel loading of a sequence

1. Click on the red x button next to the track in the Main Window. The red x will only be enabled when a track is being loaded.



How to start loading a sequence from a certain point in the timeline

1. **Alt+Left Click** on the timeline to start reloading all tracks from that point forward. This is useful when you need to check a very long sequence but are not sure where the frames that you are interested in start and you can not fit the whole sequence into RAM
-

Playback

Change the layout of the viewports

1. Click on any of the layout radio buttons in the Main Window's Control Bar. Or use keyboard keys 1 through 4 to go through the different layouts.



How to change what track is displayed on each viewport

1. Select the track you want to show (A,B,C or D) in the corresponding viewport's Track Option Box in the Main Window's Control Bar.



How transform a viewport

1. Left click and drag on a viewport to pan.
2. Use the mouse wheel to zoom in and out. Pressing shift while zooming makes the zoom 10x faster.
3. If you press the **alt** key while doing any of this, transformations will apply to all viewports (Gang Transformation).
4. If you don't have a mouse wheel, you can zoom in and out by clicking and dragging the viewport's zoom box on the Main Window's control panel. From this box you can also change the pan and rotation values.
5. You can also flip and flop the image by clicking on the **flip** and **flop** buttons.
6. You can reset the transformation on a viewport by pressing ctrl+r on your keyboard, or alt+r to reset all viewports.



How to change the aspect ratio of a viewport

1. Select or type in an aspect ratio in the viewport's **Ratio Option Box**. File is the default value, which maintains the original aspect ratio of the image.
2. You can change the aspect ratio of the image by placing black crop bars instead of deforming it by clicking the **Crop Bars Button** to the right of the Ratio Option Box.



3. You can change the position of the crop bars by clicking on the Crop Bar Position button next to the Crop Bars Button. You can place the crop bars at the top and bottom, only at the top, or only at the bottom. 

How to see only certain channels on a viewport

1. Activate or deactivate channels by clicking on the viewport's Channel Buttons, you view any combination of RGB channels, as well as visualizing the alpha transparency channel independently.



How to control the playback

1. Click on the play/pause, rewind, fast forward, back one frame and forward one.
2. Scrub the timeline by clicking and dragging the current frame notch on the timeline
3. Click on the Playback Mode Radio Buttons to control if you want to play the sequence once (Once), Loop it (Loop), or play it back and forth (Swing)

How to offset a track on the timeline

1. Click on the more options menu button next to the track on the Main Window's Control Bar 
2. Change the value of the **track offset** in the More Options Window for that track. You can type in a number or click and drag to change the value.

How to hold a specific frame on a track

1. Click on the more options menu button next to the track on the Main Window's Control Bar 
 2. Select an option from the **Hold Frame Option Box**:
 - a. **Current:** Holds the current frame
 - b. **First:** When the current frame number is smaller than the first loaded frame on the track, the first frame will be shown.
 - c. **Last:** When the current frame number is bigger than the last loaded frame on the track, the last frame will be shown.
 - d. **None:** Does not hold any frame and the track plays normally.
-

How to unload a track

1. Click on the more options menu button next to the track on the Main Window's Control Bar 
 2. Click on the **Unload Track button**.
-

How to show or hide text information

1. Press the shortcut key **t** to toggle display of information text on the viewport, or press **alt+t** to toggle it on all viewports
 2. If the track has a DPX image sequence loaded, you can display the DPX metadata for each frame by pressing the shortcut key **shift+t**
-

How to show DPX Metadata on the viewport

1. If the track has a DPX image sequence loaded, you can display the DPX metadata for each frame by pressing the shortcut key **shift+t**
-

Processing

How to Load a JefeCheck FX

1. Open the FX Manager Window (**F9** or **menu>image>FX Manager**).
 2. Click the Browse Button
 3. Select a **.jfx** file
 4. If you want to have the FX autoload next time you start JefeCheck, click on the **auto-load** checkbox next to the FX's name.
-

How to Load a LUT

1. Open the LUT Manager Window (**F10** or **menu>image>Cube Manager**).
 2. Click the Browse Button
-

3. Select a **.cube, .cub, .lut, .jlut, .bmp or .tga** file.
4. If you want to have the LUT load automatically next time you start JefeCheck, click on the **auto-load** checkbox next to the LUT's name.

How to apply one or more FXs to a viewport's FX stack

1. Open the FX Control Window (**F8 or menu>image>FX Control**)
2. Click on the Viewport where you want to apply the FX
3. Select the FX you want to apply from the Add menu in the FX Control Window.
4. Turn the FX on or off by clicking on the on/off checkbox on the FX's controls. 
5. Repeat steps 3 and 4 for each FX you want to add.

How to change the position of an FX in the FX stack

1. Click on the **Up**  or **Down**  button on the FX's controls.

Remote Session

How to start a JefeCheck Remote Session Server

1. Open the Remote Session Manager Window (**F6 or menu>Remote Session>Session Manager**).



The image shows a 'Start Server' dialog box with a dark background. It contains the following fields and buttons:

- Name:** JefeServer1
- port:** 32000
- password:** (empty text box)
- Start:** (button)
- Server IP:** (empty text box)

2. In the Start Server section of the Manager fill in the necessary information:
 - a. Type the server's name in the Server Name Text Box
 - b. Type the port the server should listen on (32000 and above recommended) in the Port Text Box

- c. Type a password in the Password Text Box (optional but recommended)
 3. Click the **Start Button**
-

How to join a JefeCheck Remote Session Server

1. Open the Remote Session Manager Window (**F6** or **menu>Remote Session>Session Manager**).



- a. Type the server's IP address
 - b. Type the port where the server you are connecting to is listening
 - c. Type a password in the Password if the server requires one
 - d. Type in a Nickname to identify yourself in the session
 3. Click the **Connect Button**
-

How to Chat in a Remote Session

1. Connect to a Remote Session
 2. Press **ctrl+y** to go into Chat Mode
 3. Type in your message
 4. Press enter to send the message.
 5. You can also navigate the previous messages by pressing **up or down on the cursor keys** on your keyboard.
 6. You can exit chat mode by pressing the **Escape** key
-

**How to use
Remote Pointers in
a Remote Session**

1. Connect to a Remote Session
2. Click anywhere on the viewport's area, everybody will see your cursor with your Nickname next to it.
3. If you click and drag your cursor will move on everybody else's session.

**How to Save a
Chat from a
Remote Session**

1. Connect to a Remote Session
 2. Chat
 3. When you are finished, click on menu>Remote Session>Save Chat
 4. Select where you want to save your session and type a filename
-