

Command Palette Dock

The Command Palette Dock is a persistent toolbar that stays visible at the edge of your screen, providing instant access to your most-used commands and extensions without needing to open the full Command Palette window.

 Note

The Dock feature is part of the Command Palette and requires Command Palette to be enabled and running in the background.

Enable the Dock

To enable the Dock, open Command Palette settings and toggle the **Enable Dock** option. When enabled, the Dock appears as a toolbar anchored to the edge of your screen.

Dock layout

The Dock is divided into three regions that organize your pinned commands:

 [Expand table](#)

Region	Position	Description
Start	Left side (or top, for vertical docks)	Primary commands and launchers. By default, includes the Home command and WinGet launcher.
Center	Middle	Additional commands you add. Initially empty.
End	Right side (or bottom, for vertical docks)	Utility widgets. By default, includes Performance Monitor and Date/Time widgets.

The Dock displays horizontally when anchored to the top or bottom of the screen, and vertically when anchored to the left or right.

Pin commands to the Dock

There are several ways to pin commands and extensions to the Dock.

Pin from Command Palette

The easiest way to add a command to the Dock is directly from the Command Palette:

- 1. Open the Command Palette and navigate to the command you want to pin.
- 2. Right-click the command and select **Pin to Dock**, or open the **More actions** menu and select **Pin to Dock**.

To remove a pinned command, right-click it and select **Unpin from Dock**.

Pin from Dock edit mode

You can also manage the Dock layout by entering edit mode:

- 1. Right-click the Dock background and select **Edit Dock**.
- 2. Select the + button in the Start, Center, or End region to add a new command.
- 3. Choose from the list of available commands in the flyout.
- 4. Drag and drop commands to reorder them within or across regions.
- 5. Select **Save** to apply your changes, or **Discard** to revert.

You can right-click individual items in edit mode to toggle **Show Titles** and **Show Subtitles**, or to **Unpin** a command from the Dock.

Pin from Dock settings

In the Command Palette settings, the **Bands** section lists all available dock bands. Use the toggle switch next to each band to pin or unpin it from the Dock.

Dock settings

The following settings are available for the Dock in Command Palette settings.

 Expand table

Setting	Description
Enable Dock	Enable a toolbar with quick access to commands.

Appearance

 Expand table

Setting	Description
Position	Choose which screen edge to anchor the Dock to: Left , Top (default), Right , or Bottom .
Theme mode	Select which theme to display: Use system settings (default), Light , or Dark .
Material	Select the visual material: Transparent or Acrylic (default).
Background colorization	Customize the Dock background. Options include None , Accent color (uses the Windows system accent color), Custom color (pick a color tint and intensity), or Image (set a background image with brightness, blur, and fit controls).

When **Image** is selected as the background colorization mode, the following additional settings are available:

 Expand table

Setting	Description
Background image	Browse for an image file (supports PNG, BMP, JPG, GIF, TIFF, WEBP, and other common formats).
Background image brightness	Adjust the brightness of the background image (–100 to 100).
Background image blur	Set the blur effect applied to the background image (0–50).
Background image fit	Choose how the background image is scaled: Fill or Stretch .

When **Custom color** or **Image** is selected, you can also configure:

 Expand table

Setting	Description
Color tint	Pick a custom color tint for the Dock background.
Color intensity	Adjust the intensity of the color tint (1–100).

Bands

The **Bands** section lists all available dock bands provided by installed extensions. Each band has a toggle switch to pin or unpin it from the Dock.

Dock behavior

The Dock uses the Windows AppBar API to reserve screen space, so other windows don't overlap it. The Dock:

- Stays visible at all times while enabled (auto-hide is not currently supported).
- Automatically restores its position if Windows Explorer restarts.
- Cannot be resized or dragged — its position is controlled by the **Position** setting.

Related content

- [Command Palette overview](#)
- [Extensibility overview](#)

Last updated on 03/17/2026