Installation Guide

Reminders for Windows 10 / 11 · free · about 2 minutes · by Digital Arts


Reminders is a small free app that sits next to the clock on your taskbar. Add as many reminders as you like, choose the days they repeat and give each one its own alarm tone.

What you need

Item	Requirement
Computer	Windows 10 or Windows 11 (32-bit or 64-bit)
Space	Less than 1 MB. Nothing else to install – .NET Framework 4.8 is already part of Windows.
Speakers	To hear the alarm tones
Internet	Only to download the file

Install


1. Download **Reminders.exe** from **apps.datpl.com** (Reminders → Download).
2. Make a folder for it, for example **Documents\Reminders**, and move **Reminders.exe** there. Keep it in this place – the Start-with-Windows shortcut points to it.
3. Double-click **Reminders.exe**. If Windows shows a blue **"Windows protected your PC"** box, click `More info` → `Run anyway`. This appears because the app is new and not yet signed; it only happens the first time.
4. The **Welcome** screen opens. Leave both boxes ticked:
   • *Start Reminders when I sign in to Windows* – so reminders ring even after a restart.
   • *Add Reminders to the Start menu*.
   Click `Start`.
5. A **bell icon** appears next to the clock. On Windows 11, if you don't see it, click the `^` arrow next to the clock. To keep it always visible: Settings → Personalization → Taskbar → **Other system tray icons** → turn **Reminders** on.




Welcome screen (first start)

Add your first reminder

1. Click the **bell icon** next to the clock. The panel opens on the right side of the screen.
2. Click `+ Add reminder` and type a name, for example *Take medicine*.
3. Set the **Time** (click the hour or minute and use the arrows or type).
4. Under **Repeat on**, tick the days it should ring – Mon to Sun. Tick all for every day. Tick none for a **one-time** reminder (it turns itself off after ringing).
5. Pick an **Alarm tone**: Bell, Temple bell, Digital beep, Birds, Melody – or **Your own MP3...** to choose a song or recording from your computer. Click `▶` to listen.
6. That's all – everything is saved by itself. Click anywhere else to close the panel.



The panel next to the clock



When a reminder rings

When a reminder rings

A popup appears at the bottom-right and the tone keeps playing. Click `Dismiss` to stop it, or `Snooze 10 min` to be reminded again. The sound stops by itself after 3 minutes; the popup stays until you close it.

Good to know

Switch a reminder off	Use the switch on the left of its name – it stays in the list.
Delete a reminder	Click ✕ on the right of its name.
Start with Windows on/off	Right-click the bell icon (or ≡ in the panel) → **Start with Windows**.
Close the app	Right-click the bell icon → **Exit**. Reminders don't ring while it is closed.
Computer was asleep	Reminders missed in the last 15 minutes still ring when it wakes up.
Update to a new version	Exit the app, replace **Reminders.exe** with the new file, open it again. Your reminders stay.
Uninstall	Exit the app, then delete **Reminders.exe**, the Start menu entry and the folder **%APPDATA%\DigitalArts\Reminders**.

Need help or software made for your business? WhatsApp **+91 99332 11177** · www.datpl.com