
CS1: Display Work Center

Exercise Display the work center that is used in CS order processing. **Time** 10 min

Task Use the SAP Fiori Launchpad to display a work center.

Name (Position) Joe Sanders (Work Scheduler)

	Work centers are master data in Production (PP), Plant Maintenance (PM), Service Management (CS), Quality Management (QM), and Project Management (PS). Work centers generally describe a workshop, a collection of machines or a group of employees. In the present case, we represent all bicycles of a given type using a work center, that means it contains a number (N) of individual capacities (each individual capacity represents one bicycle). Work centers are important for scheduling, capacity utilization checks as well as for cost calculation of orders.


To view a work center, click the *Display Work Center* app in the *Service Management* area in the *Work Scheduler* role.

Start



Enter **NY00** for the *plant* and **RNTL1000** for the *work center*.

NY00
RNTL1000




Then click Basic Data.

	The **work center type** generally controls the properties of the work center and is maintained in Customizing. The work center type used here, 0006, defines the work center as a resource, as it is used for networks (PS) or also for Plant Maintenance (PM) / Service Management (SM) (in contrast to types 0001 / 0003, which we use in Production). Moreover, the task list usage controls in which task lists (PP, PS, PM, QM, SM, ...) the work center can be assigned to operations.

On the *Display Work Center: Basic Data* screen, switch to the *Capacities* tab page.


Double-click capacity category **001** to display the header data of the capacity category.



	Capacity category 001 (“machine”) shows 999 individual capacities (corresponding to a stock of 999 bicycles), which can be used 24 hours a day (the factory calendar shows all days of the week as “working days”). Since 10% of the bicycles have to be maintained on average, 90% of the bicycles remain available for rental (utilization rate).

Return to the capacity overview from the header data. To do so, click .

Back on the *Display Work Center: Capacity Overview* screen, navigate to the *Costing* tab page.



	The work center is linked to the cost center **NABR1000** (Bike Rental) and provides (as a default value for transactions) the activity type BKRNTL ("Bike Rental"). Based on the combination of cost center and activity type, a rate of 1 USD per hour is planned in cost center accounting. Formula **SAP008** calculates the number of rental hours from the work maintained in the activity (in contrast to production, there is only one default value per activity in PM/SM orders or networks - instead of six).


Return to the SAP Fiori launchpad by choosing .

CS 2: Display Equipment

Exercise Display the equipment that is used in CS order processing. **Time** 10 min


Task Use the SAP Fiori Launchpad to display an equipment.

Name (Position) Evelyn Monroe (Shop Floor Worker)

	Equipment is part of the Plant Maintenance (PM) and Service Management (SM) master data as technical objects. You create assets or plant parts. Equipment can be assigned to notifications or orders and pass on data to these documents. In service processing, measurement data can be entered and updated for equipment, both for evaluating and planning maintenance tasks. Equipment can be linked to material serial numbers if there are several pieces of equipment of the same material (like 100 identical returnable bicycles here). In our case, we map each individual bike on loan through a piece of equipment. Later, we will send measurement documents to the devices to record the GPS position, mileage, and occupancy status for each bike on loan.

To view a piece of equipment, in the *Service Management* area, in the *Shop Floor Worker* role, click on the *Display Equipment app.*

Start




On the *Display Equipment: Initial* Screen, use the in the *Equipment* field.

In the *Equipment number (1)* pop-up window, choose to switch to the navigation menu *Equipment by Serial number list.*

Enter **CTBR1000** in the *Material* field and **###** (your three-digit number) in the *Serial Number* field.

CTBR1000
###




Click Execute. The system should find exactly one equipment number, which is automatically copied to the Equipment field.



Choose **Enter** to display the data for your equipment.

	The system displays manufacturer data such as the bike model, the manufacturer and the date of production. In our case the bike was manufactured by Global Bike in Dallas, the model is the touring bike DXTR3000.


Navigate to the *Organization* tab to display the organizational data of your equipment.






Note the assignment of your equipment to company code US00, to business area BR00, and to cost center NABR1000 ("Bike Rental"). The maintenance planning plant (later important for equipment maintenance tasks) is the plant NY00.

Switch to the *SerData* tab page to display the assignment to the material and serial number.



	As expected, you see here the material CTBR1000 and the serial number ### (because you only found your equipment through this assignment). Note that the material number is the same for all 1000 rental bicycles. However, the combination of material number and serial number is assigned uniquely and one-to-one to a equipment number.

Now click Measuring points/counters to view the measuring points assigned to your equipment.



	Measurement points are numerical features for which measurement values can be recorded. We use measurement points to record the GPS location, the mileage and the "occupied" status of our bikes. The mileage status (**NABRDIST**) can be used, for example, to perform periodic maintenance. The GPS coordinates (latitude **GPSLAT**, longitude **GPSLON**) are used to track our rental bikes (geographic analysis). The "occupied" status **BRSTATE** works like the light of a taxicab: "red" means "occupied", "green" signals "available". In fully automated rental processes, all these measurement points are recorded by sensors in the rental bike itself.

Click on SAP to return to the SAP Fiori launchpad.