

\*\*\*\*\*Draft\*\*\*\*\*  
**pshell /dev/ttyACM0**  
**or**  
**pshell /dev/ttyUSB0**  
**08/31/26**  
\*\*\*\*\*Draft\*\*\*\*\*

The following text in pshell/shell.c at main start.

```
bool uart = true;
#if LIB_PICO_STDIO_USB
while (!stdio_usb_connected())
    sleep_ms(1000);
uart = false;
#endif
```

The following text in pshell/CmakeList.txt file controls which port is used.


```
if (USB_CONSOLE)
    pico_enable_stdio_uart(${PSHELL} 0)
    pico_enable_stdio_usb(${PSHELL} 1)
else()
    pico_enable_stdio_uart(${PSHELL} 1)
    pico_enable_stdio_usb(${PSHELL} 0)
endif()
```

This statement in pshell/cmpico2

```
cmake .. -DUSB_CONSOLE=0 -DPICO_BOARD=pico2 -DPICO_PLATFORM=rp2350
```

With the change below now /dev/ttyACM0 instead of /dev/ttyUSB0

```
cmake .. -DUSB_CONSOLE=1 -DPICO_BOARD=pico2 -DPICO_PLATFORM=rp2350
```

A screenshot of a terminal window titled 'devel@pi5-70: ~'. The terminal shows the output of the 'pico2' command, which displays a configuration menu. The menu lists various settings for the serial device, including the device path (/dev/ttyACM0), lockfile location (/var/lock), callout program, baud rate (115200 8N1), and hardware/software flow control. The user is prompted to 'Change which setting?' and the terminal shows a cursor at the bottom of the menu. The status bar at the bottom of the terminal window displays 'CTRL-A Z for help | 115200 8N1 | NOR | Minicom 2.8 | VT102 | Offline | ttyACM0'.

/: version

Pico Shell , LittleFS v2.9, Vi 0.9.1, SDK v2.2.0xx

```
devel@pi5-70: ~  
File Edit Tabs Help  
  
Pico Shell - Copyright (c) 1883 Thomas Edison  
This program comes with ABSOLUTELY NO WARRANTY.  
This is free software, and you are welcome to redistribute it  
under certain conditions. See LICENSE file for details.  
  
platform: pico2, console: USB [79 X 26], filesystem: flash  
file system automatically mounted  
enter a command or hit ENTER for command list  
  
/: ls  
  
 8192 dwt.bin  
 487 hello.c  
 68 hello  
4224 img1.pgm  
12544 lena_rgb_64.bmp  
4224 lena_rgb_64.pgm  
1380 pico2-blink.c  
296 pico2-blink  
320 sine-072926  
392 sine.c  
  
/:  
CTRL-A Z for help | 115200 8N1 | NOR | Minicom 2.8 | VT102 | Offline | ttyACM0
```

XX

If the pshell/cmpico2 or pshell/cmpico are used to create the Makefile.

Without git diff ../cmpico2

diff --git a/cmpico2 b/cmpico2

index 9d30aaa..5160e09 100755

--- a/cmpico2


+++ b/cmpico2

@@ -1 +1 @@


- cmake .. -DUSB\_CONSOLE=0 -DPICO\_BOARD=pico2 -DPICO\_PLATFORM=rp2350

+ cmake .. -DUSB\_CONSOLE=1 -DPICO\_BOARD=pico2 -DPICO\_PLATFORM=rp2350

The FTDI 2 USB required as seen located in lower part of the image below.




These are the settings of the USB port.



```
devel@pi4-50: ~  
File Edit Tabs Help  
Welcome to minicom 2.8  
OPTI+-----+  
Port| A - Serial Device      : /dev/ttyUSB0  
    | B - Lockfile Location  : /var/lock  
Pres| C - Callin Program     :  
    | D - Callout Program    :  
    | E - Bps/Par/Bits       : 115200 8N1  
    | F - Hardware Flow Control : No  
    | G - Software Flow Control : No  
    | H - RS485 Enable       : No  
    | I - RS485 Rts On Send   : No  
    | J - RS485 Rts After Send : No  
    | K - RS485 Rx During Tx  : No  
    | L - RS485 Terminate Bus  : No  
    | M - RS485 Delay Rts Before: 0  
    | N - RS485 Delay Rts After : 0  
    |  
    | Change which setting?   
+-----+  
CTRL-A Z for help | 115200 8N1 | NOR | Minicom 2.8 | VT102 | Offline | ttyUSB0
```

This is USB after reboot



```
devel@pi4-50: ~  
File Edit Tabs Help  
Pico Shell - Copyright (c) 1883 Thomas Edison  
This program comes with ABSOLUTELY NO WARRANTY.  
This is free software, and you are welcome to redistribute it  
under certain conditions. See LICENSE file for details.  
platform: pico2, console: UART0 [80 X 24], filesystem: flash  
file system automatically mounted  
enter a command or hit ENTER for command list  
/: version  
Pico Shell , LittleFS v2.9, Vi 0.9.1, SDK v2.2.0  
/:
```

XX