MANAGING USERS AND PERMISSIONS IN LINUX

TYPES OF USERS IN LINUX SYSTEM

1.Root User (super user) ---> ID (0)

1. Root User is a super user (Admin) in the Linux system
2.Having all the access in the Linux system
2.Its home directory is /root
3. And its id (UID) is 0

2.System User ---> ID (1-999)

1.system user created automatically by the system to run the services and the processes
2.Usually have no login shell
2.Its id started from 1 to 999

3.Standard user (local user) ---> ID (1000+)

1.standard users are the local users created by the admin (root)
2.That having only the specific access in the Linux system
2.Its home directory should be /home/username
3.And its id started from 1000+ and so on

CREATING USER'S

1.adduser mayur / useradd mayur
2.passwd mayur
3.userdel mayur

CLOUDBLITZ

How To Switch from Root User to Local User

1.su – mayur

How To Switch from Local User to Local User

1.su – atul
Password: < >

Note: -

1.When u switch from **root user to local user** u don't want password
2.But when u switch from **local user to local user** then u must have the password

---

USER RELATED FILES

1./etc/passwd

This file basically stores all the information about the users like its userid, groupid, GCOS (comment), home directory and login shell.

Prompt: - {mayur:x:1000:1000:,,,,:/home/mayur:/bin/bash}

1.mayur ----------> username
2.X ----------> Password (it stored in the encrypted form in /etc/shadow file)
3.1000 ----------> user ID
4.1000----------> group ID
5.,,,, ---------->GECOS (comment / User info)
6./home/mayur----> Home directory
7./bin/bash----------> Login shell

HOW TO MODIFTY THE USERS' PERMISSIONS – USERMOD

1. **How to change the User ID of user**
   usermod -u 1050 mayur
2. **How to change the Group ID of user**
   usermod -g 1001 mayur
3. **How to change the Comment of a user**
   usermod -c "hey mayur" mayur
4. **How to change the Directory of a user**
   usermod -d /mnt mayur
5. **How to change the Shell of a user**
   usermod -s /bin/sh mayur

Note: -

1. When u change the group id u must assign the group id of a existing group because if u assign another group id which does not exist then u get the error.
2. If we want to check all the shells in the system, then run command: - /etc/shells

---

CLOUDBLITZ

HOW TO LOCK THE USER

1.usermod -L mayur

HOW TO UNLOCK THE USER

1.usermod -U mayur

HOW TO CHANGE THE PASSWORD OF A USER - PASSWD

1.su – mayur

mayur@localhost: ~$ passwd
current password:
new password:
retype password:

Note: -

1. When u change the password of a user from root user then u run the command passwd mayur
2. But when u change the password of a user from the user then run the command Passwd
3. Also, local user cannot change the password of another local user

---

HOW TO DELETE THE USER

1.userdel mayur

CLOUDBLITZ
