

Learning Objectives

Learners will be able to:

- Access Active Directory in the Progressive shared virtual machine.
- Search for users and groups in Active Directory.
- Reset and manage passwords in Active Directory.

Active Directory (AD) is used in the E-INS domain to manage user accounts, groups, credentials, devices, and access to applications.

Many, but **not all** permissions and groups from the E-INS domain have been built into **PIMS** entitlements, which can be used to create **Flex Roles** that provide E-INS access. This aligns with our access provisioning standards used at Progressive.

When searching users in **Active Directory**, if you are unable to locate a user, they may not yet have an account created in the **E-INS domain**.

The **PIMS** entitlement **Property IT E-INS Basic Access** triggers account creation. After the account is created, additional **PIMS entitlements** and **Flex Roles** can be added to provide further E-INS access as needed.


Active Directory Login

Active directory is accessed from within the **Progressive shared virtual machine**. The software comes **preinstalled** and is available from the Windows start menu in the **Windows Administrative Tools** folder.

To facilitate changes and support customers, you must log in to the application with admin-level credentials.


From the **Windows Administrative Tools** folder:

1. Right click **Active Directory Users and Computers** while holding **Ctrl + Shift**.
2. Select **More**, then **Run as different user**.
3. Enter credentials when prompted.



Reset a Password in Active Directory

1. **Right-click** the desired user account.
2. Select **Reset Password**.
3. **Uncheck** the first box, “**User must change password at next login.**”
4. Enter the **temporary password** in the standard password convention once you verify the user.
 - a. For the standard password convention, review: [KBA00256148: Property Home - Property VM password expired - The user accounts' password has expired.](#)
5. After the user has successfully signs in to their assigned virtual machine, instruct them to **customize their password** by pressing **Ctrl + Alt + Del** and selecting **Change a Password**.



NOTE: If the customer has the P-O-PASSWORDSYNC entitlement, changing the virtual machine password will also update their LAN password.


The customer cannot keep the temporary password as their permanent password. Temporary passwords are not secure and must be changed at login.

Adding Users to Groups in Active Directory


You **are** permitted to **add Users** to **Groups**. You are **not** permitted to **add PIMS entitlements**.

Never add database account groups memberships to customer accounts. These begin with the prefix **DB**. Groups beginning with the prefix **DB** are **legacy** and are being deprecated.


1. Locate the **e-ins.net** domain folder in the left-hand column and right-click it.
2. Select **Find**.
3. In the search window, enter the **desired group name**.



4. **Double-click** the group name to open the **Group Properties** window.



5. In the **Group Properties** window, select the **Members** tab.
6. Click **Add**.



7. In the search window, enter the **user's name**.
8. Click **OK** to add the user to the group.