The screenshots below will demonstrate the simulation diagram, switch configurations, and router configurations.



Switch0

Physical Config CLI Attributes

```
VLAN Name                             Status    Ports
---- -------------------------------- --------- -------------------------------
1    default                          active    Fa0/3, Fa0/4, Fa0/5, Fa0/6
                                                Fa0/7, Fa0/8, Fa0/9, Fa0/10
                                                Fa0/11, Fa0/12, Fa0/13, Fa0/14
                                                Fa0/15, Fa0/16, Fa0/17, Fa0/18
                                                Fa0/19, Fa0/20, Fa0/21, Fa0/22
                                                Fa0/23, Gig0/1, Gig0/2
10   sales                            active    Fa0/1
20   HR                               active    Fa0/2
1002 fddi-default                     active
1003 token-ring-default               active
1004 fddinet-default                  active
1005 trnet-default                    active
Switch#show interface trunk
Port        Mode         Encapsulation  Status        Native vlan
Fa0/24      on           802.1q         trunking      1

Port        Vlans allowed on trunk
Fa0/24      1-1005

Port        Vlans allowed and active in management domain
Fa0/24      1,10,20

Port        Vlans in spanning tree forwarding state and not pruned
Fa0/24      1,10,20

Switch#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#interface fa0/23
Switch(config-if)#switchport mode trunk
Switch(config-if)#exit
Switch(config)#exit
Switch#
%SYS-5-CONFIG_I: Configured from console by console
show interface trunk
Port        Mode         Encapsulation  Status        Native vlan
Fa0/24      on           802.1q         trunking      1

Port        Vlans allowed on trunk
Fa0/24      1-1005
```

Copy Paste

Top

Switch0

Physical Config CLI Attributes

```
Fa0/24       1,10,20

Port        Vlans in spanning tree forwarding state and not pruned
Fa0/24      1,10,20

Switch#
%LINK-5-CHANGED: Interface FastEthernet0/23, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/23, changed state to up

Switch#show interface trunk
Port        Mode         Encapsulation  Status        Native vlan
Fa0/23      on           802.1q         trunking      1
Fa0/24      on           802.1q         trunking      1

Port        Vlans allowed on trunk
Fa0/23      1-1005
Fa0/24      1-1005

Port        Vlans allowed and active in management domain
Fa0/23      1,10,20
Fa0/24      1,10,20

Port        Vlans in spanning tree forwarding state and not pruned
Fa0/23      none
Fa0/24      1,10,20

Switch#





Switch con0 is now available




Press RETURN to get started
```

Copy Paste

Top

- These screenshots display the configurations of switch 0

Switch1

Physical Config CLI Attributes

```
%SYS-5-CONFIG_I: Configured from console by console
show vlan brief

VLAN Name                             Status    Ports
---- -------------------------------- --------- -------------------------------
1    default                          active    Fa0/3, Fa0/4, Fa0/5, Fa0/6
                                                Fa0/7, Fa0/8, Fa0/9, Fa0/10
                                                Fa0/11, Fa0/12, Fa0/13, Fa0/14
                                                Fa0/15, Fa0/16, Fa0/17, Fa0/18
                                                Fa0/19, Fa0/20, Fa0/21, Fa0/22
                                                Fa0/23, Gig0/1, Gig0/2
10   sales                            active    Fa0/1
20   HR                               active    Fa0/2
1002 fddi-default                     active
1003 token-ring-default               active
1004 fddinet-default                  active
1005 trnet-default                    active
Switch#show interface trunk
Port        Mode         Encapsulation  Status        Native vlan
Fa0/24      on           802.1q         trunking      1

Port        Vlans allowed on trunk
Fa0/24      1-1005

Port        Vlans allowed and active in management domain
Fa0/24      1,10,20

Port        Vlans in spanning tree forwarding state and not pruned
Fa0/24      1,10,20

Switch#



Switch con0 is now available
```

Copy Paste

Top

- Switch configurations for router 1

Router0

Physical Config CLI Attributes

```
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface g0/0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

Router(config-if)#interface g0/0.10
Router(config-subif)#
%LINK-3-UPDOWN: Interface GigabitEthernet0/0.10, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0.10, changed state to up
encapsulation dot1q 10
Router(config-subif)#ip address 192.168.10.1
% Incomplete command.
Router(config-subif)#ip address 192.168.10.1 255.255.255.0
Router(config-subif)#exit
Router(config)#interface g0/0.20
Router(config-subif)#
%LINK-3-UPDOWN: Interface GigabitEthernet0/0.20, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0.20, changed state to up
encapsulation dot1q 20
Router(config-subif)#ip address 192.168.20.1 255.255.255.0
Router(config-subif)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
show ip interface
GigabitEthernet0/0 is up, line protocol is up (connected)
  Internet protocol processing disabled
GigabitEthernet0/0.10 is up, line protocol is up (connected)
  Internet address is 192.168.10.1/24
  Broadcast address is 255.255.255.255
  Address determined by setup command
  MTU is 1500 bytes
  Helper address is not set
  Directed broadcast forwarding is disabled
  Outgoing access list is not set
  Inbound  access list is not set
```

Copy Paste

Top

Router0

Physical Config CLI Attributes

```
  Address determined by setup command
  MTU is 1500 bytes
  Helper address is not set
  Directed broadcast forwarding is disabled
  Outgoing access list is not set
  Inbound  access list is not set
  Proxy ARP is enabled
  Security level is default
  Split horizon is enabled
  ICMP redirects are always sent
  ICMP unreachables are always sent
  ICMP mask replies are never sent
  IP fast switching is disabled
  IP fast switching on the same interface is disabled
  IP Flow switching is disabled
  IP Fast switching turbo vector
  IP multicast fast switching is disabled
  IP multicast distributed fast switching is disabled
  Router Discovery is disabled
  IP output packet accounting is disabled
  IP access violation accounting is disabled
  TCP/IP header compression is disabled
  RTP/IP header compression is disabled
  Probe proxy name replies are disabled
  Policy routing is disabled
  Network address translation is disabled
  BGP Policy Mapping is disabled
  Input features: MCI Check
  WCCP Redirect outbound is disabled
  WCCP Redirect inbound is disabled
  WCCP Redirect exclude is disabled
GigabitEthernet0/0.20 is up, line protocol is up (connected)
  Internet address is 192.168.20.1/24
  Broadcast address is 255.255.255.255
  Address determined by setup command
  MTU is 1500 bytes
  Helper address is not set
  Directed broadcast forwarding is disabled
  Outgoing access list is not set
 --More--
```

Copy Paste

Top

-Router 0 configurations