



Handleiding - pfSense Captive Portal


Ga naar Services → Captive Portal



Maak een zone aan (klik op add):



Gebruik exact deze instellingen voor de zone, voor de rest alles default laten:



Interfaces: VLAN 15 GAST (bij mij OPT10)

Reset waiting period	☐ Enable waiting period reset on attempted access If enabled, the waiting period is reset to the original duration if access is attempted when all pass-through credits have already been exhausted.
Logout popup window	☒ Enable logout popup window If enabled, a popup window will appear when clients are allowed through the captive portal. This allows clients to explicitly disconnect themselves before the idle or hard timeout occurs.
Pre-authentication redirect URL	 Set a default redirection URL. Visitors will be redirected to this URL after authentication only if the captive portal doesn't know where to redirect them. This field will be accessible through \$PORTAL_REDURL\$ variable in captiveportal's HTML pages.
After authentication Redirection URL	 Set a forced redirection URL. Clients will be redirected to this URL instead of the one they initially tried to access after they've authenticated.
Blocked MAC address redirect URL	 Blocked MAC addresses will be redirected to this URL when attempting access.
Preserve users database	☐ Preserve connected users across reboot If enabled, connected users won't be disconnected during a Netgate pfSense Plus reboot.
Concurrent user logins	Multiple Disabled: Do not allow concurrent logins per username or voucher. Multiple: No restrictions to the number of logins per username or voucher will be applied. Last login: Only the most recent login per username or voucher will be granted. Previous logins will be disconnected. First login: Only the first login per username or voucher will be granted. Further login attempts using the username or voucher will not be possible while an initial user is already active.

Authentication

Authentication Method	Use an Authentication backend Select an Authentication Method to use for this zone. One method must be selected. - "Authentication backend" will force the login page to be displayed and will authenticate users using their login and password, or using vouchers. - "None" method will force the login page to be displayed but will accept any visitor that clicks the "submit" button. - "RADIUS MAC Authentication" method will try to authenticate devices automatically with their MAC address without displaying any login page.
Authentication Server	Local Database You can add a remote authentication server in the User Manager . Vouchers could also be used, please go to the Vouchers Page to enable them.
Secondary authentication Server	Local Database You can optionally select a second set of servers to to authenticate users. Users will then be able to login using separated HTML inputs. This setting is useful if you want to provide multiple authentication method to your users. If you don't need multiple authentication method, then leave this setting empty.
Reauthenticate Users	☐ Reauthenticate connected users every minute If reauthentication is enabled, request are made to the server for each user that is logged in every minute. If an access denied is received for a user, that user is disconnected from the captive portal immediately. Reauthentication requires user credentials to be cached in the captive portal database while a user is logged in; The cached credentials are necessary for the portal to perform automatic reauthentication requests.
Local Authentication Privileges	☒ Allow only users/groups with "Captive portal login" privilege set

HTTPS Options

Login	☐ Enable HTTPS login When enabled, the username and password will be transmitted over an HTTPS connection to protect against eavesdroppers. A server name and certificate must also be specified below.
--------------	---

 Save

Local database aanduiden, waarom:
 Vouchers worden lokaal beheerd, ideaal voor secretariaat.

Dan ga je naar de Vouchers tab en maakt een nieuwe Roll met deze instellingen:

Services / Captive Portal / GUEST_PORTAL / Vouchers / Edit

Voucher Rolls

Roll #

1

Enter the Roll# (0..65535) found on top of the generated/printed vouchers

Minutes per ticket

720

Defines the time in minutes that a user is allowed access. The clock starts ticking the first time a voucher is used for authentication.

Count

20

Enter the number of vouchers (1..1023) found on top of the generated/printed vouchers. WARNING: Changing this number for an existing Roll will mark all vouchers as unused again

Comment

Dagtoegang voor gasten

Can be used to further identify this roll. Ignored by the system.

Save

Minutes per ticket: 720

(12u lang geldig)

Nog instellingen voor de Vouchers:

Create, Generate and Activate Rolls with Vouchers

Enable ☒ Enable the creation, generation and activation of rolls with vouchers

Create, Generate and Activate Rolls with Vouchers

Voucher Public Key

```
-----BEGIN PUBLIC KEY-----
MCQwDQYJKoZIhvcNAQEBBQADAwEAIIJAIjR5uyx9SYFAgMBAAE=
-----END PUBLIC KEY-----
```

Paste an RSA public key (64 Bit or smaller) in PEM format here. This key is used to decrypt vouchers. [Generate new keys](#)

Voucher Private Key

```
-----BEGIN RSA PRIVATE KEY-----
MD4CAQACCQCI0ebssfUmBQIDAQABAggHSyLQLyYWEQIFAKCe1/
cCBQDaEUrjAgQD
aBm1AgUAKIUMVQIEeFKIgA==
-----END RSA PRIVATE KEY-----
```

Paste an RSA private key (64 Bit or smaller) in PEM format here. This key is only used to generate encrypted vouchers and doesn't need to be available if the vouchers have been generated offline.

Character set

Tickets are generated with the specified character set. It should contain printable characters (numbers, lower case and upper case letters) that are hard to confuse with others. Avoid e.g. 0/O and l/1.

of Roll bits

Reserves a range in each voucher to store the Roll # it belongs to. Allowed range: 1..31. Sum of Roll+Ticket+Checksum bits must be one Bit less than the RSA key size.

of Ticket bits

Reserves a range in each voucher to store the Ticket# it belongs to. Allowed range: 1..16. Using 16 bits allows a roll to have up to 65535 vouchers. A bit array, stored in RAM and in the config, is used to mark if a voucher has been used. A bit array for 65535 vouchers requires 8 KB of storage.

of Checksum bits

Reserves a range in each voucher to store a simple checksum over Roll # and Ticket#. Allowed range is 0..31.

Magic number

Magic number stored in every voucher. Verified during voucher check. Size depends on how many bits are left by Roll+Ticket+Checksum bits. If all bits are used, no magic number will be used and checked.

Invalid voucher message

Error message displayed for invalid vouchers on captive portal error page (\$PORTAL_MESSAGES).

Expired voucher message

Error message displayed for expired vouchers on captive portal error page (\$PORTAL_MESSAGES).

[Save](#)

Klik op "Generate new keys"

Dit zijn cryptografische sleutels (RSA) die pfSense gebruikt om:

vouchers **te genereren**

vouchers **te controleren**

te voorkomen dat iemand zelf geldige codes kan verzinnen

Private key

→ wordt gebruikt om vouchers aan te maken

Public key

→ wordt gebruikt om vouchers te controleren

Firewall rules

Deze exacte firewall rules zijn nodig op het gasten VLAN interface in deze exacte **volgorde**:

Firewall / Rules / OPT10

Floating

WAN

LAN

WAN2

LAN2

LAN3

LAN4

OPT5

OPT6

OPT7

OPT8

OPT9

OPT10

OVPN_SCHOOL

IPsec

OpenVPN

Rules (Drag to Change Order)

	States	Protocol	Source	Port	Destination	Port	Gateway	Queue	Schedule	Description	Actions
☐	✗	0/0 B	IPv4 *	*	*	192.168.1.0/24	*	none		Block guest access to LAN	    
☐	✓	0/0 B	IPv4 TCP	*	*	This Firewall	80 (HTTP)	*	none	Allow HTTP to this firewall	    
☐	✓	0/0 B	IPv4 TCP/UDP	*	*	This Firewall	53 (DNS)	*	none	Allow DNS to this firewall	    
☐	✓	0/0 B	IPv4 *	*	*	*	*	none		Allow internet for authenticated guests	    

 Add

 Add

 Delete

 Toggle

 Copy

 Save

 Separator

Regel 1: Block guest access to LAN

Blokkeert alle verkeer van gasten naar het interne LAN, de pfSense managementinterface en interne servers.

Regel 2: Allow HTTP to this firewall

Laat HTTP-verkeer toe naar de firewall. Nodig om de captive portal te tonen.

Regel 3: Allow DNS to this firewall


Laat DNS-verkeer toe naar pfSense. Nodig voor hostname, captive portal detectie.

Regel 4: Allow internet for authenticated guests

Laat alle verkeer toe vanaf het gastenvlan, maar alleen NA succesvolle login. Deze regel is nodig na authenticatie.


Testen op client

Connect met OZCS-TechWiz-Gast



Je wordt normaal gezien automatisch naar de Captive portal gebracht, indien dit niet automatisch gebeurt klik op “Open browser and connect”

Gebruikt dan een voucher code en login.



Test of je internet hebt.