

Enabling Hyper-V on Windows 11 Pro / Enterprise / Education

1. Introduction

Before you enable Hyper-V on Windows, it's important to verify that your computer supports hardware virtualization.

Hyper-V relies on virtualization features built into your processor and motherboard. If these features aren't available or aren't enabled in your computer's BIOS/UEFI, Hyper-V won't run.

This guide explains the minimum requirements, how to check whether your PC is compatible, and how to enable Hyper-V on Windows.


2. Minimum System Requirements

Your computer should meet the following requirements:

Requirement	Description
Operating System	Windows 10/11 Pro, Enterprise, or Education (Hyper-V is not available on Windows Home by default.)
Processor	64-bit CPU with Second Level Address Translation (SLAT)
RAM	Minimum 4 GB (8 GB or more recommended)
Virtualization	Intel VT-x or AMD-V enabled in BIOS/UEFI
DEP	Hardware-enforced Data Execution Prevention (DEP) enabled

Confirm your Windows edition

- Go to settings
- Click on the system
- Click on about



Check the edition

System > About

Device name	DESKTOP-TDQL10M
Processor	Intel(R) Core(TM) i7-8665U CPU @ 1.90GHz (2.11 GHz)
Installed RAM	16.0 GB (15.8 GB usable)
Graphics card	Intel(R) UHD Graphics 620 (128 MB)
Storage	117 GB of 477 GB used
Device ID	C359F9B3-A58C-4B39-9255-65EDC1A33520
Product ID	00330-80000-00000-AA864
System type	64-bit operating system, x64-based processor
Pen and touch	No pen or touch input is available for this display

Related links [Domain or workgroup](#) [System protection](#) [Advanced system settings](#)

Windows info


Copy ^

Edition	Windows 11 Pro
Version	24H2
Installed on	8/1/2025
OS build	26100.8737
Experience	Windows Feature Experience Pack 1000.26100.334.0


[Microsoft Services Agreement](#)
[Microsoft Software License Terms](#)

3. Confirm that visualization is enabled

- Open Task Manager



- Select performance
- Click CPU
- Look for virtualization: enabled



Once you've confirmed your PC meets the Hyper-V system requirements, enabling the feature takes only a few steps.


Step 1: Open Windows Features

Click the Start button or press the Windows key.

In the search box, type:

Turn Windows features on or off

Select the matching result.



Step 2: Enable Hyper-V


The **Windows Features** window will open.

Scroll down until you find **Hyper-V**

Check the **Hyper-V** checkbox.

Windows will automatically select the required Hyper-V components.

Click **OK**.



Step 3: Install the Feature

Windows will begin searching for the required files and installing Hyper-V.

Wait for the installation to complete.

When prompted, click Restart now


Your computer must restart before Hyper-V becomes available.

Step 4: Verify Hyper-V Was Installed


After Windows restarts:

1. Click Start.
2. Search for Hyper-V Manager

If Hyper-V Manager appears in the search results, the installation was successful.



Hyper-V is now enabled and ready to use. You can launch Hyper-V Manager to create and manage virtual machines for testing, learning, or running multiple operating systems on the same computer.



Divine