

Name: Diya Shah

Assignment: Print Server Configuration in Windows Server

1. Install the Print Server Role and Add a Network Printer

Steps:

1. Open Server Manager.
2. Click Manage → Add Roles and Features.
3. Select Role-based or feature-based installation.
4. Choose the local server and click Next.
5. Under Server Roles, expand Print and Document Services.
6. Select Print Server and click Add Features.
7. Click Next and then Install.
8. After installation, open Server Manager → Tools → Print Management.
9. Expand Print Servers → <Server Name> → Printers.
10. Right-click Printers → Add Printer.
11. Select Add a new network printer (or add Microsoft XPS Document Writer if a physical printer is unavailable).
12. Complete the wizard.

Result: The Print Server role is installed successfully, and the printer is added in Print Management.

2. Configure Print Permissions

Steps:

1. Create two local user accounts:
 - User1
 - User2
2. Open Print Management.
3. Right-click the shared printer → Properties.
4. Open the Security tab.
5. Remove the Everyone group if required.
6. Add User1 and User2.

7. Configure permissions:
 - User1: Allow Print
 - User2: Deny Print
8. Click Apply and OK.

Result: User1 can print documents, while User2 is denied permission to print.

3. Test Printing and Monitor the Print Queue

Steps:

1. Log in as User1.
2. Print a test document (e.g., Notepad).
3. Open Print Management and view the printer queue.
4. Verify that the print job appears and is processed successfully.
5. Log in as User2.
6. Attempt to print the same document.
7. Observe the result in the print queue.

Observation

User	Result	Reason
------	--------	--------

User1	Print job succeeds	User has Print permission.
-------	--------------------	----------------------------

User2	Print job fails	User is denied Print permission.
-------	-----------------	----------------------------------

Result: Only the allowed user can submit and print documents. The denied user receives an access denied error or the job is not accepted.

4. Change Print Job Priority

Steps:

1. Submit two print jobs:
 - One from User1
 - One from another allowed user
2. Open Print Management.
3. Open the printer queue.
4. Right-click the print job you want to prioritize.
5. Select Properties.

6. Increase the Priority value (e.g., 99).
7. Leave the other job with a lower priority (e.g., 1).
8. Resume printing if paused.

Observation

Although one print job was submitted later, it prints before the earlier job because it has a higher priority.

Result: Print job priority successfully controls the order in which documents are printed.

5. Configure Permissions for Event Managers and Volunteers

Steps:

1. Create two local groups:
 - Event Managers
 - Volunteers
2. Add users to the appropriate groups.
3. Open Print Management.
4. Right-click the printer → Properties → Security.
5. Configure permissions:
 - Event Managers
 - Allow Print
 - Allow Manage Documents
 - Volunteers
 - Allow Print
 - Do not allow Manage Documents
6. Click Apply and OK.

Testing

Login as an Event Manager

- Print a document.
- Pause, resume, or cancel print jobs.

Result: Successfully prints and manages print jobs.

Login as a Volunteer

- Print a document.
- Attempt to pause or cancel another user's print job.

Result: Can print documents but **cannot** pause, resume, or cancel print jobs because the **Manage Documents** permission is not granted.