

Warehouse Management System


Date: Aug 2021


Prepared by: Allen Chen

Version: V2.1

Updated: 2023-05-23








Install


Download apk file and install.

Link as below : http://172.28.30.24:9090/w ms.apk











Login

- 1.Enter your account.
- 2.Enter password.
- 3. Select plant from list.
- 4.Enter server (172.28.30.24:8085).
- 5.Click "Sign in".

PDA need to access the server(172.28.30.24) via WIFI







Issue material

Please select a printer if you need to print label.


WH Filter: Filter warehouse

Filter: Filter material, e.g. 27-XXX

Order: Work order, e.g. 331000018411


To-location: If the actual quantity exceed actual demand, need to input buffer location, e.g. ZS01 – ZS30.






- 1.Input material or work order and press enter, system will download material list and stock information from SAP automatically.
- 2. Sort by work order and material.
- 3. You can skip the current material if you need.









- 4.Scan the batch number or QR Code and press enter, System will show the stock quantity automatically.
- 5. Click the save button and confirm.









- 6. The system will skip to the next material automatically.
- 7. If the actual quantity exceed actual demand, you need input the to-location(e.g. ZS01, ZS02...).
- 8. You can change the actual quantity yourself.

Buffer





Buffer

- 1.Click "Leftover".
- 2. Select one or more record from item list.
- 3.Click the "Save " button.




Structure Editor: Display IT_ZBESTAND from Entry 1




6 Entries

WERK MATNR	LGOR	CHARG	S	POSID	LABST	ERSDA
8101 27-301971-000-R000 8101 27-301971-000-R000 8101 27-301971-000-R000 8101 27-301971-000-R000 8101 27-301971-000-R000 8101 27-301971-000-R000	AC27 AC27 AC27 SZ00	0008390797 0008390801 0008390802 0008390795			27, 500. 000 12, 500. 000 2, 500. 000 2, 572, 000	04/13/2022 04/13/2022 04/13/2022 04/13/2022 04/13/2022 04/13/2022



Buffer

The actual demand is 200 pcs, actual release quantity is 205, the exceeded quantity is 5pcs(205-200), location already change from AC27 to ZS01.







PO: 110001340597 P/N: 27-301971-000-R000 QTY: 205 Batch: 0008390795 MFP: HEF4053BT NXP MFN: AC27 Location: 2022-06-09 Date: , - A -- MILLER MANNER PROPERTY -- THE PARKET BERT

Issue material

Once material issued, material labels will be printed out from system automatically. PDA need connect to the selected network printer, each printer should set a separate WIFI account, password and IP address. The label format as below. If we need to re-print any label, we can scan its QR-Code or input the batch number and press enter.

Re-print label





Re-print

- 1.Click "Re-print".
- 3. Select a printer from list.
- 3.Scan batch number or QR-Code, system will print label automatically.





Seq.	Data Item	Description
1	P/N	VTech Material Number
2	Batch	VTech Batch Number
3	Pack No.	Package Number
4	Plant	Plant Code
5	QTY	Package Quantity
6	Stock Flag	Special Stock flag
7	WBS	Production Log
8	Vendor	Vendor Code
9	Bin	Bin Code
10	INV	Vendor Invoice / Delivery Note Number
11	PO	VTech PO Number
12	MPN	Manufacturer Part Number
13	MFN	Manufacturer Name


2, 二维码标签内容数据格式。

每个数据字段由 # 号分隔,并按以上顺序固定排列,最后以;号结尾。

49-100991-000-R000#0005941364#1/1#8501#301###14221##D20200317001# 8510082305#80-010233-004-R000#VTECHMETAL;



Issue material flow chart



Issue material flow chart

As picture



PO Receive

PO receive - PC



	Pack Qty	Label Qty
▶	30	3
	5	1
	3	1
	2	1

	P/N	Total Qty	Allow Qty	Location	Ntgew	РО
> 2	27-107000-000-R000	30730.000	30730.000	RS01	0.264	8110389269
2	27-307122-000-R000	354.000	354.000	RS01	0.802	8110389269
2	27-307634-000-R000	2985.000	2985.000	RS01	2.501	8110389269


O/ Line	On Qty	On Dute
0068	7500.000	2022-04-01
0067	3230.000	2022-04-01
0069	2500.000	2022-04-11
0055	5000.000	2022-04-11
0056	2500.000	2022-04-11
0054	7500.000	2022-05-03
0032	2500.000	2022-05-16
System msg 8110389269 receive successfully		
	0068 0067 0069 0055 0056 0054 0032 System msg	0068 7500.000 0067 3230.000 0069 2500.000 0055 5000.000 0056 2500.000 0032 2500.000 System msg X


PO Receive

OA Date

- 1.Input gito, invoice no or delivery no.
- 2.Input PO and press enter, will download list from SAP automatically.
- 3. Select record from list.
- 4.Input receive quantity, pack quantity, label quantity and press enter.
- 5.Click the save button to submit the data.

PO receive - PDA






PO Receive


- 1.Choose the scan or manual.
- 2.Scan QR-Code if you choose the type is "Scan QR-code".
- 3.Invoice#, PO#, Batch# and quantity will be download from system automatically.

2 way can be used to receive goods, first is to scan the QR code, then related PO#, batch# and qty. etc. will automatically show up and we do not need input one by one.

2nd way is manual receiving, we then have to input invoice#, PO#, qty. etc.

PO receive - PDA







PO Receive

- 4. Choose the material from item list.
- 5. The outstanding PO line, OA line will automatically pop up from system.
- 6. Save your record after input completed.

PO receive - PDA






PO Receive


7.System will automatically show up the message and doc number.




Move location

Move location








Move location

- 1.Select a plant from list.
- 2.Scan material QR_Code or input material and batch number.
- 3.Input old location and new location.
- 4. Click the "Save" button.



FG-In & FG-Out







Flow

- 1.Prod scan serial number in process(TXX,WWW,PKR...).
- 2.VTS will upload output(confirmation) to SAP automatically.
- 3.FG-In(Serial doc number, carton sn or customer sn).
- 4.FG-Out(DN, carton sn or customer sn)









FG-In

- 1.Click "FG-In".
- 2.Select a plant, e.g. 8101,5301, 6501
- 3. Select sn type.
- 4. Input doc number and press enter.
- 5.Input product name and location.
- 6.Scan serial number (Carton SN & Product SN).










FG-In

- 1.Scan sn one by one.
- 2.If the sn is incorrect, system will show the error message.



















FG-Out

- 1.Click "FG-Out".
- 2.Select a pant, e.g. 8101,5301,6501.
- 3. Select sn type.
- 4.Input DN number and press enter.
- 5.Scan serial number(Carton SN & Product SN).











Location label print

Location

Location label print






Location label print

- 1.Click "Location print".
- 2. Select a print from list.
- 3.Enter location, e.g. From "AA05" to "AA07", System will print "AA05", "AA06" and "AA07".

Location label print






Material label print





vtech



Login

- 1.Input your id and password.
- 2.Select PRD or QAS.
- 3.Click the "Login" button.






RT label print


- 1. User ID is required and you can skip po#, material and date.
- 2.Click "Query" button to preview label list.
- 3. Select item from list and submit.
- 4.Click "Print" button and select a printer.
- 5. Current label list will be printed out from system automatically.

Material label print




RT label print







RT label re-print




Re-print

- 1.Input batch number.
- 2.Input print quantity.
- 3.Click "Query" button to download data from SAP.
- 4.Click "Preview" button to preview label list.
- 5.If you change the print quantity, need click"Query" and "Preview" button again.

RT label re-print

Page 1 of 17



Re-print


6.Click "Print" button and select a printer.

7. Current label list will be printed out from system automatically.



☑ □ □ 100% -

RT label re-print one by one



Re-print

You can input the quantity and print label one by one.







Reports



Issue material query







Query

- 1.Click"Issue material query".
- 2. Select a plant from list.
- 3.Input or scan work order, will show data in list.

Stock query





Stock Query

- 1.Click"Stock query".
- 2. Select a plant from list.
- 3.Input p/n, batch or location, will show data in list (following red rectangle)



Thank You