0

Reads the current controller real-time clock into the working date/time array

Current controller time component

GSV
Class Name WallClockTime
Instance Name
Attribute Name DateTime
Dest RTC_DateTime[0]
0

1

stores the timestamp for the e-stop fault the first time the condition becomes true

Raw E-stop condition
Cond_EStop

One-shot storage for E-stop tiimestamping
ONS_EStop_TS
ONS

Timestamp for e-stop fault

MOVE
Source RTC_DateTime[0]
0
Dest TS_EStop[0]
0

Timestamp for e-stop fault

MOVE
Source RTC_DateTime[1]
0
Dest TS_EStop[1]
0

Timestamp for e-stop fault

MOVE
Source RTC_DateTime[2]
0
Dest TS_EStop[2]
0

Timestamp for e-stop fault

MOVE
Source RTC_DateTime[3]
0
Dest TS_EStop[3]
0

Timestamp for e-stop fault

MOVE
Source RTC_DateTime[4]
0
Dest TS_EStop[4]
0

Timestamp for e-stop fault

MOVE
Source RTC_DateTime[5]
0
Dest TS_EStop[5]
0

Timestamp for e-stop fault

MOVE
Source RTC_DateTime[6]
0
Dest TS_EStop[6]
0

2

stores the timestamp for the motor overload fault the first time it occcurs

Raw motor overload condition
Cond_MotorOL

One-shot storage for motor overload timestamp
ONS_MotorOL_TS
ONS

Timestamp for motor overload
MOVE
Source RTC_DateTime[0]
0
Dest TS_MotorOL[0]
0

Timestamp for motor overload
MOVE
Source RTC_DateTime[1]
0
Dest TS_MotorOL[1]
0

Timestamp for motor overload
MOVE
Source RTC_DateTime[2]
0
Dest TS_MotorOL[2]
0

Timestamp for motor overload
MOVE
Source RTC_DateTime[3]
0
Dest TS_MotorOL[3]
0

Timestamp for motor overload
MOVE
Source RTC_DateTime[4]
0
Dest TS_MotorOL[4]
0

Timestamp for motor overload
MOVE
Source RTC_DateTime[5]
0
Dest TS_MotorOL[5]
0

Timestamp for motor overload
MOVE
Source RTC_DateTime[6]
0
Dest TS_MotorOL[6]
0

3

Stores the timestamp for the high temperature fault

Raw high temperature fault
Cond_HighTemp

One-shot storage for High temp timestamp
ONS_HighTemp_TS
ONS

Timestamp for high temp
MOVE
Source RTC_DateTime[0]
0
Dest TS_HighTemp[0]
0

Timestamp for high temp
MOVE
Source RTC_DateTime[1]
0
Dest TS_HighTemp[1]
0

Timestamp for high temp
MOVE
Source RTC_DateTime[2]
0
Dest TS_HighTemp[2]
0

Timestamp for high level
MOVE
Source RTC_DateTime[3]
0
Dest TS_HighLevel[3]
0

Timestamp for high level
MOVE
Source RTC_DateTime[4]
0
Dest TS_HighLevel[4]
0

Timestamp for high temp
MOVE
Source RTC_DateTime[5]
0
Dest TS_HighTemp[5]
0

Timestamp for high temp
MOVE
Source RTC_DateTime[6]
0
Dest TS_HighTemp[6]
0

4

Stores the timestamp for the high temp fault

Raw low temp fault
Cond_LowTemp

One-shot storage for low temp timestamp
ONS_LowTemp_TS
ONS

Timestamp for low temp
MOVE
Source RTC_DateTime[0]
0
Dest TS_LowTemp[0]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[1]
0
Dest TS_LowTemp[1]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[2]
0
Dest TS_LowTemp[2]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[3]
0
Dest TS_LowTemp[3]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[4]
0
Dest TS_LowTemp[4]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[5]
0
Dest TS_LowTemp[5]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[6]
0
Dest TS_LowTemp[6]
0

5

Stores the timestamp for the high level fault

Raw high level fault
Cond_Highlevel

One-shot storage for high level timestamp
ONS_HighLevel_TS
ONS

Timestamp for high level
MOVE
Source RTC_DateTime[0]
0
Dest TS_HighLevel[0]
0

Timestamp for high level
MOVE
Source RTC_DateTime[1]
0
Dest TS_HighLevel[1]
0

Timestamp for high level
MOVE
Source RTC_DateTime[2]
0
Dest TS_HighLevel[2]
0

Timestamp for high level
MOVE
Source RTC_DateTime[3]
0
Dest TS_HighLevel[3]
0

Timestamp for high level
MOVE
Source RTC_DateTime[4]
0
Dest TS_HighLevel[4]
0

Timestamp for high level
MOVE
Source RTC_DateTime[5]
0
Dest TS_HighLevel[5]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[6]
0
Dest TS_LowTemp[6]
0

6

Stores the timestamp for the low level fault

Raw low level fault
Cond_Lowlevel

One-shot storage for low level timestamp
ONS_LowLevel_TS
ONS

Timestamp for low level
MOVE
Source RTC_DateTime[0]
0
Dest TS_LowLevel[0]
0

Timestamp for low level
MOVE
Source RTC_DateTime[1]
0
Dest TS_LowLevel[1]
0

Timestamp for low level
MOVE
Source RTC_DateTime[2]
0
Dest TS_LowLevel[2]
0

Timestamp for low level
MOVE
Source RTC_DateTime[3]
0
Dest TS_LowLevel[3]
0

Timestamp for low level
MOVE
Source RTC_DateTime[4]
0
Dest TS_LowLevel[4]
0

Timestamp for low level
MOVE
Source RTC_DateTime[5]
0
Dest TS_LowLevel[5]
0

Timestamp for low temp
MOVE
Source RTC_DateTime[6]
0
Dest TS_LowTemp[6]
0

7

Stores the timestamp for the valve 1 failure fault

Raw low level fault
Cond_Valve1Fail

One-shot storage for valve 1 fault timestamp
ONS_Valve1_TS
ONS

Timestamp for valve 1 fault
MOVE
Source RTC_DateTime[0] 0
Dest TS_Valve1Fail[0] 0

Timestamp for valve 1 fault
MOVE
Source RTC_DateTime[1] 0
Dest TS_Valve1Fail[1] 0

Timestamp for valve 1 fault
MOVE
Source RTC_DateTime[2] 0
Dest TS_Valve1Fail[2] 0

Timestamp for valve 1 fault
MOVE
Source RTC_DateTime[3] 0
Dest TS_Valve1Fail[3] 0

Timestamp for valve 1 fault
MOVE
Source RTC_DateTime[4] 0
Dest TS_Valve1Fail[4] 0

Timestamp for valve 1 fault
MOVE
Source RTC_DateTime[5] 0
Dest TS_Valve1Fail[5] 0

Timestamp for valve 1 fault
MOVE
Source RTC_DateTime[6] 0
Dest TS_Valve1Fail[6] 0

8

Stores the timestamp for the valve 2 failure fault

Raw valve 1 failure
Cond_Valve2Fail

One-shot storage for valve 2 fault timestamp
ONS_Valve2_TS
ONS

Timestamp for valve 2 Fault
MOVE
Source RTC_DateTime[0]
0
Dest TS_Valve2Fail[0]
0

Timestamp for valve 2 Fault
MOVE
Source RTC_DateTime[1]
0
Dest TS_Valve2Fail[1]
0

Timestamp for valve 2 Fault
MOVE
Source RTC_DateTime[2]
0
Dest TS_Valve2Fail[2]
0

Timestamp for valve 2 Fault
MOVE
Source RTC_DateTime[3]
0
Dest TS_Valve2Fail[3]
0

Timestamp for valve 2 Fault
MOVE
Source RTC_DateTime[4]
0
Dest TS_Valve2Fail[4]
0

Timestamp for valve 2 Fault
MOVE
Source RTC_DateTime[5]
0
Dest TS_Valve2Fail[5]
0

Timestamp for valve 2 Fault
MOVE
Source RTC_DateTime[6]
0
Dest TS_Valve2Fail[6]
0

9

Stores the timestamp for the valve 3 failure fault

Raw valve 2 failure
Cond_Valve3Fail

One-shot storage for valve 3 fault timestamp
ONS_Valve3_TS
ONS

Timestamp for valve 3 fault
MOVE
Source RTC_DateTime[0]
0
Dest TS_Valve3Fail[0]
0

Timestamp for valve 3 fault
MOVE
Source RTC_DateTime[1]
0
Dest TS_Valve3Fail[1]
0

Timestamp for valve 3 fault
MOVE
Source RTC_DateTime[2]
0
Dest TS_Valve3Fail[2]
0

Timestamp for valve 3 fault
MOVE
Source RTC_DateTime[3]
0
Dest TS_Valve3Fail[3]
0

Timestamp for valve 3 fault
MOVE
Source RTC_DateTime[4]
0
Dest TS_Valve3Fail[4]
0

Timestamp for valve 3 fault
MOVE
Source RTC_DateTime[5]
0
Dest TS_Valve3Fail[5]
0

Timestamp for valve 3 fault
MOVE
Source RTC_DateTime[6]
0
Dest TS_Valve3Fail[6]
0

10

Stores the timestamp for the sensor fault when it first occurs

Raw valve 3 failure
Cond_SensorFault

One-shot storage for sensor fault timestamp
ONS_Sensor_TS
ONS

Timestamp for sensor fault
MOVE
Source RTC_DateTime[0] 0
Dest TS_SensorFault[0] 0

Timestamp for sensor fault
MOVE
Source RTC_DateTime[1] 0
Dest TS_SensorFault[1] 0

Timestamp for sensor fault
MOVE
Source RTC_DateTime[2] 0
Dest TS_SensorFault[2] 0

Timestamp for sensor fault
MOVE
Source RTC_DateTime[3] 0
Dest TS_SensorFault[3] 0

Timestamp for sensor fault
MOVE
Source RTC_DateTime[4] 0
Dest TS_SensorFault[4] 0

Timestamp for sensor fault
MOVE
Source RTC_DateTime[5] 0
Dest TS_SensorFault[5] 0

Timestamp for sensor fault
MOVE
Source RTC_DateTime[6] 0
Dest TS_SensorFault[6] 0

(End)