## NAME

**mbm_tmap** − Macro to convert XYZ point clouds to 3D Tiles and generate a Cesium viewer.

## VERSION

Version 5.0

## SYNOPSIS

**mbm_tmap -I***pointcloud.xyz* [**-O***tiles_dir*] [**-P***port*] [**--serve-only** | **--no-convert**] [**-N**] [**-S**] [**-W**] [**-V**] [**-H**]

## DESCRIPTION

**mbm_tmap** is a macro that automates point cloud web visualization setup. It runs **py3dtiles convert** on an input XYZ point cloud file, writes an **index.html** Cesium viewer file into the output tiles directory, and can optionally start a local HTTP server using **python -m http.server**.

By default **mbm_tmap** performs conversion from XYZ input. If **--serve-only** (or **--no-convert**) is specified, conversion is skipped and an existing tiles directory is served directly.

This macro is intended for quick local testing and browsing of tiled point cloud data products.

## MB-SYSTEM AUTHORSHIP

David W. Caress
Monterey Bay Aquarium Research Institute
Dale N. Chayes
Center for Coastal and Ocean Mapping
University of New Hampshire
Christian do Santos Ferreira
MARUM - Center for Marine Environmental Sciences
University of Bremen

## OPTIONS

**−I** *pointcloud.xyz*
Input XYZ point cloud file. This option is required unless **--serve-only** or **--no-convert** is specified.

**−O** *tiles_dir*
Output directory for 3D Tiles and generated **index.html**. Default is **tiles**.

**−P** *port*
HTTP server port used when starting **python -m http.server**. Default is **8000**.

**--serve-only, --no-convert**
Skip **py3dtiles** conversion and serve an existing tiles directory. In this mode **-O** should point to an existing tiles directory. If **index.html** already exists it is reused.

**−N**
Do not open a browser automatically.

**−S**
Do not start a local HTTP server.

**−W**
Wait on the server process after starting it. Use Ctrl+C to stop.

**−V**
Verbose output.

**−H**
Print help message and exit.

## EXAMPLES

Convert an XYZ file to tiles and start local server:
**mbm_tmap -I cloud.xyz -O tiles -V**

Serve an existing tiles directory without reconversion:
**mbm_tmap --serve-only -O tiles -P 8081 -W -V**

Convert an XYZ file to tiles without starting server:
**mbm_tmap -I cloud.xyz -O tiles -S**

Start server and keep the macro attached to server lifetime:
**mbm_tmap -I cloud.xyz -O tiles -W**

## SEE ALSO

**mbgrd2gltf**(1), **mbsystem**(1)

## BUGS

No known bugs.