impdp -help信息

[oracle@rac01 ~]\$ impdp -help Import: Release 11.2.0.4.0 - Production on Tue Jan 23 10:30:43 2018 Copyright (c) 1982, 2011, Oracle and/or its affiliates. All rights reserved. The Data Pump Import utility provides a mechanism for transferring data objects between Oracle databases. The utility is invoked with the following command: Example: impdp scott/tiger DIRECTORY=dmpdir DUMPFILE=scott.dmp You can control how Import runs by entering the 'impdp' command followed by various parameters. To specify parameters, you use keywords: Format: impdp KEYWORD=value or KEYWORD=(value1, value2,..., valueN) Example: impdp scott/tiger DIRECTORY=dmpdir DUMPFILE=scott.dmp USERID must be the first parameter on the command line. The available keywords and their descriptions follow. Default values are listed within square brackets. ATTACH Attach to an existing job. For example, ATTACH=job name. CLUSTER Utilize cluster resources and distribute workers across the Oracle RAC. Valid keyword values are: [Y] and N. CONTENT Specifies data to load.e Valid keywords are: [ALL], DATA_ONLY and METADATA_ONLY. DATA_OPTIONS Data layer option flags. Valid keywords are: SKIP CONSTRAINT ERRORS. DIRECTORY Directory object to be used for dump, log and SQL files. DUMPFILE List of dump files to import from [expdat.dmp]. For example, DUMPFILE=scott1.dmp, scott2.dmp, dmpdir:scott3.dmp. ENCRYPTION PASSWORD Password key for accessing encrypted data within a dump file. Not valid for network import jobs. **ESTIMATE** Calculate job estimates. Valid keywords are: [BLOCKS] and STATISTICS. EXCLUDE Exclude specific object types. For example, EXCLUDE=SCHEMA: "='HR'". FLASHBACK_SCN SCN used to reset session snapshot. FLASHBACK TIME Time used to find the closest corresponding SCN value. Import everything from source [Y]. HELP Display help messages [N]. INCLUDE Include specific object types. For example, INCLUDE=TABLE_DATA. JOB_NAME Name of import job to create.

LOGFILE

Log file name [import.log].

NETWORK_LINK

Name of remote database link to the source system.

NOLOGFILE

Do not write log file [N].

PARALLEL

Change the number of active workers for current job.

PARFILE

Specify parameter file.

PARTITION OPTIONS

Specify how partitions should be transformed.

Valid keywords are: DEPARTITION, MERGE and [NONE].

QUERY

Predicate clause used to import a subset of a table.

For example, QUERY=employees: "WHERE department_id > 10".

REMAP_DATA

Specify a data conversion function.

For example, REMAP DATA=EMP. EMPNO: REMAPPKG. EMPNO.

REMAP_DATAFILE

Redefine data file references in all DDL statements.

REMAP_SCHEMA

Objects from one schema are loaded into another schema.

REMAP TABLE

Table names are remapped to another table.

For example, REMAP_TABLE=HR.EMPLOYEES:EMPS.

REMAP TABLESPACE

Tablespace objects are remapped to another tablespace.

REUSE_DATAFILES

Tablespace will be initialized if it already exists [N].

SCHEMAS

List of schemas to import.

SERVICE NAME

Name of an active Service and associated resource group to constrain Oracle RAC resources.

SKIP_UNUSABLE_INDEXES

 ${\ensuremath{\mathsf{Skip}}}$ indexes that were set to the Index Unusable state.

 $SOURCE_EDITION$

Edition to be used for extracting metadata.

SQLFILE

Write all the SQL DDL to a specified file.

STATUS

Frequency (secs) job status is to be monitored where

the default [0] will show new status when available.

STREAMS_CONFIGURATION

Enable the loading of Streams metadata

 $TABLE_EXISTS_ACTION$

Action to take if imported object already exists.

Valid keywords are: APPEND, REPLACE, [SKIP] and TRUNCATE.

TABLES

Identifies a list of tables to import.

For example, TABLES=HR. EMPLOYEES, SH. SALES: SALES_1995.

TABLESPACES

Identifies a list of tablespaces to import.

TARGET_EDITION

Edition to be used for loading $\ensuremath{\mathsf{metadata}}.$

TRANSFORM

 ${\tt Metadata\ transform\ to\ apply\ to\ applicable\ objects.}$

 $\begin{tabular}{lll} Valid keywords are: OID, PCTSPACE, SEGMENT_ATTRIBUTES and STORAGE. \\ \end{tabular}$

TRANSPORTABLE

Options for choosing transportable data movement.

Valid keywords are: ALWAYS and [NEVER].

Only valid in NETWORK_LINK mode import operations.

TRANSPORT DATAFILES

List of data files to be imported by transportable mode.

 $TRANSPORT_FULL_CHECK$

Verify storage segments of all tables [N].

TRANSPORT_TABLESPACES

List of tablespaces from which metadata will be loaded.

Only valid in NETWORK_LINK mode import operations.

VERSION

Version of objects to import.

Valid keywords are: [COMPATIBLE], LATEST or any valid database version.

Only valid for NETWORK_LINK and SQLFILE.

The following commands are valid while in interactive mode.

Note: abbreviations are allowed.

CONTINUE CLIENT

Return to logging mode. Job will be restarted if idle.

EXIT_CLIENT

Quit client session and leave job running.

HELP

Summarize interactive commands.

KILL_JOB

Detach and delete job.

PARALLEL

Change the number of active workers for current job.

START_JOB

Start or resume current job.

Valid keywords are: SKIP_CURRENT.

STATUS

Frequency (secs) job status is to be monitored where

the default [0] will show new status when available.

STOP_JOB

Orderly shutdown of job execution and exits the client.

Valid keywords are: IMMEDIATE.

[oracle@rac01 ~]\$