

PUSH POSSIBLE™

MANHATTAN SCALE™

VOCOLLECT CONFIGURATION GUIDE

VOCOLLECT CONFIGURATION GUIDE

Copyright and Disclaimer

Copyright © 2026 Manhattan Associates, Inc. All rights reserved.

This documentation, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. The information in this documentation is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Manhattan Associates, Inc. ("Manhattan"). No third-party patent liability is assumed with respect to the use of the information contained herein. While every precaution has been taken in the preparation of this documentation, Manhattan assumes no responsibility for errors or omissions.

EXCEPT WHERE EXPRESSLY PROVIDED OTHERWISE, ALL CONTENT, MATERIALS AND INFORMATION, ARE PROVIDED ON AN "AS IS" AND "AS AVAILABLE" BASIS. MANHATTAN EXPRESSLY DISCLAIMS ALL WARRANTIES OF ANY KIND, WHETHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.

Except as permitted by license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted, in any form by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Manhattan Associates.

Manhattan Associates is a registered trademark of Manhattan Associates, Inc.

All other brands, products, or services are trademarks, registered trademarks, or service marks of their respective companies or organizations.

Contact Address:

Manhattan Associates, Inc.
2300 Windy Ridge Parkway,
Atlanta, Georgia 30339

<http://www.manh.com/>

Region	Telephone	Email
Americas	+1 877.756.7435 (U.S. and Canada only) +1 404.965.4025	callcenter@manh.com
Asia	(00) 800.988.0885 (China only) +86 21 3311 3499	asiacustomersupport@manh.com
Europe, Middle East, and Africa	+44 (0) 1344 318400 (UK) +31 (0)30 214 3400 (NL)	emeacustomersupport@manh.com
Australia	+61 1300787050	aucustomersupport2@manh.com

Unsure whom to contact? Call +1 404.965.4025 and you will be routed to the appropriate support group.

VOCOLLECT CONFIGURATION GUIDE

Confidentiality

Rights to the Content of This Work

This material is protected by the Copyright Act of 1976, as amended, as an unpublished work and the foregoing notice and legend shall not be deemed to constitute publication or an intent to publish there under. These materials are proprietary and confidential information of Manhattan Associates, Inc., and may not be disclosed and used only as authorized in the License Agreement and Confidentiality Agreement controlling such disclosure and use.

Modification to the Content of This Work

Manhattan Associates, Inc. reserves the right, at any time and without notice, to change these materials or any of the functions, features or specifications of any of the software described herein. Manhattan Associates shall have no warranty obligation with respect to these materials or the software described herein, except as provided in Manhattan Associates' software license agreement with an authorized licensee.

Trademarks and Copyrights

Manhattan Associates and Manhattan Associates SCALE are trademarks of Manhattan Associates, Inc. All other company and product names may be trademarks of their respective owners. The information contained herein is subject to change without notice.

Revisions

Date	Description	Applies to build
August 8, 2016	Removed version and added revisions table with specific build level.	14.0.0314.0
June 10, 2019	Updated the Artisan file	16.0.0699.0

Table of Contents

Revisions	3
Vocollect Voice Configuration	1
Configure Vocollect Voice	1
Vocollect Artisan Emulator	2
Configuring and Deploying Vocollect Artisan Emulator	2

Vocollect Voice Configuration

Configure Vocollect Voice

SCALE supports several functions of Vocollect Voice-Directed Work, allowing the following functions:

- Outbound Picking (Both User and System Directed Work).
 - Short Picking
 - Pick into tote
 - Picking of Lot Tracked Inventory
- Packing
 - Pick into shipping container during outbound pick

The Vocollect task packages assume that numeric (not alpha) check digits and containers are used for validation during voice picking (if configured to use check digit and container validation).

Basic Configuration Steps:

Install the **Vocollect VoiceDirect** software as outlined in the *Vocollect Voice Console Implementation Guide*. Unless otherwise directed by your Vocollect vendor, follow the *Standard Installation Procedure* for Vocollect VoiceConsole.

Note: Vocollect Voice requires the Vocollect VoiceDirect software and Vocollect hardware (e.g. headsets and Talkman terminals). VoiceDirect constitutes a number of things including Voice Console & Voice Client. The software and hardware must be purchased from Vocollect (<http://www.vocollect.com/>). See the Release Notes document for more details.

1. Log into Vocollect VoiceDirect as per Vocollect documentation to load the SCALE Vocollect task file. These files can be found on the *Manhattan SCALE <version> Vocollect* distribution under the *Vocollect* folder.

There are two types of Tasks supported with SCALE. You can find the Task file zip to import as indicated below on the *Manhattan SCALE <version> Vocollect* media:

- TaskBuilder: [Media]\Vocollect\TaskBuilder\Vocollect_TaskBuilder_TaskFile.zip
- Artisan: [Media]\Vocollect\Artisan\Vocollect_Artisan_TaskFile.zip

2. Create a task package.

VOCOLLECT CONFIGURATION GUIDE

3. Create a device profile.
4. Create operator(s).
5. Configure Vocollect Talkman devices.
 - a. Load device (i.e., connect the device to a server where software is loaded).
 - b. Assign task package to the device (e.g., Talkman). Repeat for each device.
 - c. Assign operator to the device.
 - d. Train device.
7. Enable and start the "SCALE Vocollect Service" on the application server hosting Vocollect.

Vocollect setup instructions provide details on software and task file configuration. Contact your Vocollect representative for additional information. See the SCALE Online Help | Before You Begin: Vocollect Setup Notes for more details on the SCALE configuration.

Note: When using Vocollect Voice, the IP address in "%SCALE_HOME%\Executables\ILSIntegrationService.exe.config" needs to be set to the IP address of the machine where the "SCALE Integration Service" is running. The value below is what needs to be updated:

<Vocollect>

<add key="serverName" value="127.0.0.1" />

8. On premise Vocollect supports only a single environment. Which is the SCALE default environment. Always default environment must be named "Defaultaabf6698-37ae-45ee". This is true even in the case of multi environment set up.

Vocollect Artisan Emulator

Configuring and Deploying Vocollect Artisan Emulator

The Artisan emulator does not require VoiceConsole to be online or configured and can be used to interact with SCALE Vocollect functionality. Instead of audio being presented, all prompts are text-based. The LUD messages can also be seen, to assist with any debugging activities when implementing Vocollect with SCALE.

1. Copy the Artisan Emulator (*Vocollect Artisan Emulator-04262019.zip*) found in the *Manhattan SCALE <version> Vocollect* media in the \Vocollect\Artisan\ folder.
2. Extract the contents to the SCALE server or another machine with network access to the SCALE server. (i.e. C:\ArtisanEmulator)

VOCOLLECT CONFIGURATION GUIDE

3. Once extracted, locate and edit the *properties.ini* file using notepad or another text editor. Edit the following property files as outlined below. All other values should be left with the default value unless directed differently by Vocollect or your implementer. These values allow you to connect to the target SCALE server. You can then emulate communication normally facilitated by VoiceConsole.

- LUTHost – The IP address of the SCALE server running the SCALE Vocollect service.
- ODRHost – The IP address of the SCALE server running the SCALE Vocollect service.
- Operator.ID – The user profile ID in SCALE you are using the emulator with.
- Device.ID – the ID of the Vocollect device you wish to emulate to SCALE.
- Operator.Name – the user profile ID in SCALE you are using the emulator with.

Sample Property File Configurations:

```
[Application]
properties:
    applicationURI,/VocollectTask1.0/
    useHTTPServer,false
    httpServerPort,80
    sendUDPBroadcast,false
    TaskRevision,CT-42-03-001
    LUTHost, 10.100.156.43
    LUTPort,11100
    ODRHost, 10.100.156.43
    ODRPort,11100
    imageHost,http://YOUR-IMAGE-SERVER-HERE/
    SaveState,false
    SiteName,Default
    CollectVehicleInfo,true

[Environment]
properties:
    SwVersion.Locale,SwVersion.Locale
    Operator.Id,dgoldman
```

VOCOLLECT CONFIGURATION GUIDE

```
Device.Id,1234512345  
  
Operator.Name,dgoldman
```

4. To run the emulator, open up the command prompt (cmd) and navigate to the path where the emulator was extracted to (ie. C:\ArtisanEmulator)
5. Enter command:

```
C:\ python run_vad.py
```

Emulator Usage Tips:


For "Ready", you may just press enter.

Enter a Dash (-) to end the application.

To simulate a scan, add a # to the beginning of the values provided in the emulator.

Values provided in the emulator are case-sensitive for any alpha characters provided (ie. Checkdigits).

Otherwise, respond to prompts as you would when using a Vocollect device.



```
C:\Windows\system32\cmd.exe - python run_vad.py  
  
Setting Application property useHTTPServer = false  
Setting Application property httpServerPort = 80  
Setting Application property sendUDPBroadcast = false  
Setting Application property TaskRevision = CT-42-03-001  
Setting Application property LUTHost = 10.100.156.43  
Setting Application property LUTPort = 11100  
Setting Application property ODRHost = 10.100.156.43  
Setting Application property ODRPort = 11100  
Setting Application property imageHost = http://YOUR-IMAGE-SERVER-HERE/  
Setting Application property SaveState = false  
Setting Application property SiteName = Default  
Setting Application property CollectVehicleInfo = true  
Setting Environment property SwVersion.Locale = SwVersion.Locale  
Setting Environment property Operator.Id = shnaik  
Setting Environment property Device.Id = 1234512345  
Setting Environment property Operator.Name = shnaik  
  
prTaskLUTCoreConfiguration<'06-20-14 16:02:04','1234512345','SwVersion.Locale'  
    ['Manhattan SCALE on CU2013UPDATE','shnaik',1,0,'']  
prTaskLUTCoreBreakTypes<'06-20-14 16:02:06','1234512345','shnaik'  
    ['','','0','']  
Welcome to the Manhattan SCALE on CU2013UPDATE system. Current operator is shnai  
k. Say ready :  
Password?<pp> : 123  
123, correct?<pp> : yes_
```