

Level Editor & Panels - Usage Guide

Bloody Good Curry — SofaSpuds Engine


Introduction

This document explains the Level Editor and its various panels in the SofaSpuds custom engine. The editor is built using ImGui and allows developers and designers to view, modify, and test gameplay elements in real time.

1. Viewport Controls

The Viewport Controls panel manages the visualization of the game world and the editor interface.

- Editor Enabled (F10): Toggles the in-game editor UI on or off.
- Game Full Width (F11): Expands viewport across full window for testing without editor clutter.
- Undo transformation, spawn, delete of object
- Game Width/Height sliders: Adjust visible viewport size (0–100%) to test scaling and aspect ratios.
- Play / Stop: Starts or pauses the simulation (Logic, Physics, Audio systems).
- State: Playing/Stopped: Indicates current game state.
- View Height: Zoom control for orthographic camera.
- Camera Enabled: Switch between static editor camera and player-follow camera.
- Undo feature which undo action like translation, scaling ,rotate, spawning and deleting object
- Glow draw which will draw a circle that resemble light
- Eraser enable easier deleting of object by holding left mouse button




2. Hierarchy Panel

Lists all active GameObjects in the current level. Selecting an object highlights it in the viewport.

Supports:

- Click to select and inspect GameObject.
- Right-click to delete object or select object and press delete in the keyboard
- Hover to show tooltips with ID and component summary.
- Used together with the Inspector Panel to modify selected object properties.



3. Asset Browser

Displays imported assets such as textures, audio clips, and prefabs.


- Shows thumbnail previews for texture assets by clicking Textures
- Drag-and-drop functionality for applying textures to GameObjects by dragging texture to the spawn texture to change the texture of object.
- Replace or refresh asset files directly.
- Auto-refreshes assets when updated externally.



4. JSON Editor

Used to edit level or prefab JSON files directly within the engine.

- click Refresh Json to get the updated Json file
- Browse available JSONs from the data folder by clicking Select Json file
- Select the available json file to edit
- Edit the Json file by changing value
- Save changes to disk instantly.
- Enables debugging of prefab configurations and edit level.



5. Performance Viewer

Displays timing data for each engine system per frame to help identify bottlenecks.

- Shows performance percentages for systems (e.g., Physics 5%, Graphics 30%).
- Includes graph of frame time history.
- Assists in profiling and runtime optimization.
- short cut key is F1 to see this panel
- Check **Allocator mode**: it should say **Custom pooled pages (UseCPPMemManager=false)**. If it says system new/delete, your pool isn't being used.
- Spawn/load lots of objects: **Objects in use** and **Allocations** should increase. If capacity is exceeded, **Pages in use** will also increase (pool grows by adding pages).
- Delete objects: **Objects in use** should drop, **Frees** should increase, and **Free objects** should increase (memory is returned to the pool for reuse, not destroyed).
- Spawn again after deleting: **Pages in use** should stay mostly the same (reusing **Free objects**) instead of constantly growing.
- Click **Validate Pages**: **Validation issues** should be **0** (non-zero means memory corruption; details appear in the console).


8. Audio Panel

The Audio Panel controls playback and management of audio assets within the engine.

- Lists sound assets (BGM, SFX, Voice).
- Play, pause, and stop buttons for previewing sounds.
- Master, Music, and SFX volume sliders.
- Reload and import audio files (.wav, .mp3).
- Displays playback state and channel debug info.
- Integrated with the AudioSystem for runtime control.




9. Debug overlay



- Click Hitboxes to turn on or off hitboxes

10. Properties Editor

Properties Editor can edit the component of the object by selecting the object (click on object) and make changes to it.



11. Inspector Window

- Select an object and able read the components of the object.




12. Crash Test

- Use for debugging and crash testing





13. Animation Editor

- To use this panel click on view and enable Animation editor
- The Animation Editor allows you to define animation clips for your characters and objects. You can create new animations (like 'Idle', 'Run', 'Attack'), set their speed (FPS), and define which frames of a sprite sheet they use
- Choose which animation action the object is using
- Copy the relative path of the directory of the spritesheet
- Edit the Total frame, Rows, Column, start frame, end frame and fps based on the spritesheet.




14. Gizmos

- To use gizmos press S to change to scale, T for Translation and R for rotation of the object




15. Debug asset manager

- Refresh asset update the latest asset list
- Create object Prefab will create a json file with transform and render component
- Create Enemy Prefab will create json file with Transform, render, sprite Animation, RidgidBody , EnemyHealth, EnemyAttack, EnemyDesicionTree and Audio component.




16.Layers

- Spawn layer to choose which layer to spawn at in the spawn panel the default is background. Only object in the same layer will affect each other collision.
- Background layer is always behind follow by gameplay, Foreground and UI.
- Sub layer 0 is always to most behind in the category and object will be higher as the number increase to 20
- Enable all the see all Layer
- Enable selected to see only selected layer
- Checkbox tick to see certain layers



17. Particle /VFX preset Editor

- The Particle / VFX Preset Editor is a live-tuning window used to preview and adjust gameplay particle effects directly inside the editor. It currently supports three preset groups: Enemy Death Burst, Run Trail and Hit Impact VFX



-From this editor adjust the setting to change the particle effect by press Save Preset

-Can turn on Auto preview which will appear on a selected object

-Preview Enemy Death which will temporarily show the particle in the selected object

-If Use selected object is not selected it will use Manual preview Pos


- can Load the json file if you manual make changes on particle_vfx_presets.json



18. Build Size analyzer

How To Use

1. Open the Build Size Analyzer window from the View menu. Click Refresh to update the analyzer after assets have been added, removed, or changed
2. Review the asset table, which lists every asset in the project together with its file size.
3. Use the checkbox beside each asset to choose whether it should be included in the export.
4. Use Select All to include every asset, or Deselect All to clear the current selection.
5. Check the Total Selected Size display to monitor how large the current export will be.
6. Click Export Selected when ready to export.
7. In the export popup, enter a destination folder or click Browse In Editor to choose one.
8. Click Export to copy all selected assets to the chosen folder. The exported files keep their original relative folder structure.



18. shortcut key

- f1 to open performance viewer
- f11 to go window mode
- press delete to delete a selected object
- f9 crash game (debugging)
- S R T in stop mode for Scale rotate and transform gizmos
- f10 to enable editor
- p to enable fps
- control Z to undo button

