Killstreaks Addon

For Modular Multiplayer FPS Engine

Getting Started

Killstreaks Plugin
- Killstreak Slots
- Settings
- Killstreak use weapons
- UI Prefabs

Killstreak Configuration Files
- General
- UAV
- Airstrike
- Helicopter

Killstreaks Map Prefab / Map Settings
- Commander
- UAV
  - UAV Scanner
- Airstrike
- Helicopter

Getting Started

Refer to the “Quick Start.pdf” that can be found just next to this file. It contains a guide on how to quickly get started!

Killstreaks Plugin

The Heart of the Addon is the “Killstreaks Plugin” file. It can be found in the “GameData” folder inside the Plugin folder (“314 Arts/Plugins/Killstreaks”; every mentioned folder will be in that folder, unless stated otherwise).

Killstreak Slots

You could refer to them as the amount of killstreaks that you can “equip”. Every killstreak file that is in the “Possible Killstreaks” array can be equipped in the Killstreak menu that appears in the Pause Menu.

The “Use Key” is the key on your Keyboard which will be used to call a killstreak in that you have earned from that specific slot. By default, these are set to (Alpha) 6 to 8 in order to not conflict with the default weapon setup that comes with the kit.

Settings

There are a few setting bools you can mess around with.
“Can Get Killstreak Multiple Times”: Determines if you can only have one killstreak of that type in your inventory at a time. If it is set to true you could earn e.g. a Helicopter multiple times (you need to die in between).
“Bots Can Use Instant Use Killstreaks”: Determines if bots will call in killstreaks that just require a button press.
“Bots Can Use Location Killstreaks”: Determines if bots will call in killstreaks that require a specified location. If set to true, they will call it in on their location.
“Display When Killstreak Is Unlocked”: If set to true, the popup will appear notifying you that you have just earned a killstreak.

Killstreak use weapons

These are “weapons” that will be injected into the Kit’s Weapon Manager. If the “Use Animation” variable on a killstreak is set to the index of one of those weapons, they will be equipped and unequipped when the killstreak is called in. By default this is the Radio [0] and Laptop [1].

UI Prefabs

The Killstreaks Addon instantiates variable UIs at runtime. You can modify the looks of these prefabs to your liking.
“Hud Prefab”: The HUD of the Killstreaks that displays your inventory of earned killstreaks.
“Menu Prefab”: This is what shows up when you press the “Killstreaks” button in the pause menu in order to select which killstreaks you want to earn.
“Location Chooser Prefab”: This is what allows you to choose a location on the map when e.g. calling in an airstrike. The way that works is that a camera is placed above the map which renders the Minimap layer. Removing the Minimap completely (module, not just unhiding it) will

make players disappear from it. If you do not bake the Minimap for the scene, you will not see your map. It is not recommended to actually render your map from above at real time due to performance reasons.

Killstreak Configuration Files

General

All killstreaks share these settings:
“Unlocked At Kills”: How many kills do you need to get without dying in order to unlock this killstreak?
“Hud Display Sprite”: The UI sprite that the player sees in his HUD.
“Menu Preview Text”: Text that is shown in the “Killstreaks” menu in the pause menu.
“Menu Preview Sprite”: UI sprite that goes along with the text
“Use Animation”: This is the index of the weapon that you want to appear when calling in this killstreak.

UAV

“Uav Prefab”: This prefab is the actual UAV that flies around in the scene.

Airstrike

“Airstrike Prefab”: This is not the plane. This is the controller that will actually spawn the Planes accordingly to the scene settings.

Helicopter

“Helicopter Prefab”: This is the actual helicopter that will fly around in the scene and devastate enemies.

Killstreaks Map Prefab / Map Settings

The three default maps that come with the kit have default settings that should be loaded upon dragging the prefab into the map for a quick setup.

Commander

“Source”: Audio Source that will play commander voices
“Killstreak Voices”: Here you can assign voices for every killstreak.
“Ready For Deployment”: Plays when the local player has unlocked the killstreak
“Friendly Online”: Plays when a friendly killstreak was called in by you or one of your teammates.
“Enemy Online”: Plays when an enemy killstreak was called in by the enemy team.

UAV

“Start Position”: Spawn Point of UAV
“Circling Start Position”: When this point is reached, the UAV will fly slower.
“Circling End Position”: This marks the end point of the UAV. Afterwards it will go away.
“End Position”: The actual end position. This should be out of viewing distance. The UAV will go away.
“Uav Arrival Time”: How long it takes from “Start” to “Circling Start”
“Uav Life Time”: How long it takes from “Circling Start” to “Circling End”
“Uav Departure Time”. How long it takes from “Circling End” to “End”
“Xp gained Upon Destruction”: How much XP you earn when shooting down an enemy UAV.

UAV Scanner

This is the actual scanner that will make enemies appear on the map.
“Scanner Start Pos”: From where it starts to scan.
“Scanner End Pos”: When this point is reached, the scan starts again
“Scanner Time”: How long one full scan takes.

Airstrike

“Plane Prefab”: Actual Plane prefab, this is what you see flying over the map.
“Amount Of Planes”: How many planes will drop bombs
“Plane Spawn Time”: Time between spawning each plane. The first one spawns instantly.
“Plane Altitude”: Y-Coordinate of planes.
“Plane Speed”: How quickly planes fly over the map
“Spawn Point Distance”: How far away the planes spawn/end
“Distance At Which Drop Starts”: How many meters before the center (player selected point on the map) the first bomb will be dropped
“Amount of Bombs”: How many bombs *each* plane drops
“Time Between Bomb Drops”: How many seconds need to pass after each bomb until the next one is dropped?
“Bomb Prefab”: This is the actual bomb that is dropped

“Bomb Drop Start Velocity”: Velocity with which bombs start to drop
“Xp gained Upon Destruction”: How much XP you earn when shooting down an enemy Plane

Helicopter

“Spawn Points”: Possible points where helicopter can start to exist
“Helicopter Live Time”: Time in seconds the helicopter flies around on the map and kills enemies
“Helicopter Hovering Time”: x = min; y = max; time helicopter spends on every hover point until moving on to another one
“Helicopter Smooth”: SmoothDamp smooth value (essentially the speed).
“Hovering Points”: Points in the world space where the helicopter will hover. You can drag these around in the scene view “White outlined squares”. You should place these where the helicopter has a good view around your map
“Xp Gained Upon Destruction”: How much xp you gain after you shot down an enemy helicopter