



INTERNAL DOCUMENT

ERP System – Standard Operating Procedures

Detailed Process Flowchart & Module-wise SOP Guide

12
Modules

7
User Roles

End-to-End
Process Flow


Table of Contents

1. System Overview & End-to-End Flow	3
2. Module SOPs	4
2.1 Lead & Enquiry Management	4
2.2 Quotation & BOQ Builder	4
2.3 Project Creation	5
2.4 Bill of Materials (BOM) & Budget	5
2.5 Milestones & Payment Schedule	6
2.6 Purchase Orders & Procurement	6
2.7 Warehouse & Stock Management	7
2.8 Material Requests & Issues	7
2.9 Manufacturing Jobs & Job Cards	8
2.10 Quality Control (QC)	8
2.11 Site Delivery & Installation	9
2.12 Invoicing & Collections	9
3. Role & Access Matrix	10
4. Auto-Generated Code Reference	11
5. Key Business Rules	11

1. System Overview – End-to-End Process Flow

Complete journey from first client enquiry to final payment collection

CRM & Sales Projects Inventory Factory / MES Site Finance Decision / Gate



2. Module-wise Standard Operating Procedures

Step-by-step guide for each module with inputs, outputs and responsible roles

2.1 Lead & Enquiry Management



Logging a New Lead

ROLE: SALES

- 1 Go to **CRM & Sales** → **Leads & Enquiries**
- 2 Click + **New Lead**
- 3 Enter: Client name, phone, email, location, requirement
- 4 Select source (Referral / Walk-in / Social / etc.)
- 5 Set initial status to **New**
- 6 Save — lead code auto-generates (ENQ/001)

INPUT

Client contact,
requirement details,
source

OUTPUT

Lead record with auto-
code ENQ/001



Follow-up & Conversion

ROLE: SALES

- 1 Update lead status: New → Followed Up → Qualified
- 2 Add follow-up notes and next action date
- 3 If interested: create a **Quotation** from the lead
- 4 If not interested: mark as **Lost** with reason
- 5 Converted leads automatically link to the quotation

STATUSES

New → Followed Up →
Qualified → Converted /
Lost

OUTPUT

Qualified lead → triggers
Quotation creation

2.2 Quotation & BOQ Builder



Creating a BOQ

ROLE: SALES / CEO

- 1 Go to **CRM & Sales** → **Quotations** → **Open BOQ**
- 2 Fill: Client name, site address, designer, validity
- 3 Click + **Add Room** for each space (Bedroom, Kitchen...)
- 4 Within each room, add line items: Description, Unit, Qty, Rate
- 5 Amount auto-calculates per item; Grand Total updates live
- 6 Fill Terms: Payment terms, warranty, scope includes/excludes
- 7 Click **Save** — returns to Quotations list

INPUT

Room-wise items with qty
& rates

OUTPUT

Quotation with auto ref
STR/Q/001



Preview & Send to Client

ROLE: SALES / CEO

- 1 On the quotation list, click **Preview**
- 2 Choose template: **Classic / Modern / Minimal**
- 3 Review the formatted quotation document
- 4 Click **Print / PDF** → Save as PDF
- 5 Share PDF with client via email/WhatsApp
- 6 Update status to **Sent** after sharing

Templates: Classic (dark gold), Modern (blue),
Minimal (black & white). Template choice persists
during the session.

2.3 Project Creation



Convert Quotation to Project

ROLE: CEO / ADMIN

- 1 Set quotation status to **Approved**
- 2 Click **Convert to Project** button on the quotation row
- 3 System auto-creates: Project code (P001), Client name, Contract value
- 4 All BOQ line items become **Products** under the project
- 5 Each product carries the quoted price from the BOQ
- 6 Project appears in **Projects** module with status: Planning

INPUT

Approved quotation

OUTPUT

Project P001 + products with quoted prices




Adding Products Manually

ROLE: CEO / FACTORY SUPERVISOR

- 1 Go to **Projects** → **Products**
- 2 Select the project from the filter dropdown
- 3 Click **+ Add Product** — project is pre-filled automatically
- 4 Enter: Product name, category, estimated cost, notes
- 5 Save — product linked to the current project

Categories: Wardrobe, Kitchen, TV Unit, Study, Cot/Bed, Shoe Rack, Loft, Pooja Unit, Dining, Bathroom Vanity, Other.

2.4 Bill of Materials (BOM) & Budget



Setting Up Project BOM

ROLE: CEO / FACTORY SUPERVISOR

- 1 Go to **Projects** → **Project BOM**, select project
- 2 **Material BOM tab:** Add each raw material — select from warehouse items or type custom. Enter Budget Qty and Waste %. Net Qty auto-calculates.
- 3 **Labour BOM tab:** Add work centres (Carpentry, Site Installation, etc.). Enter hours and rate — amount auto-calculates.
- 4 **Other Costs tab:** Enter Transport, Expenses, Contingency
- 5 **Milestones tab:** Default 30/40/30 schedule pre-filled. Edit names, amounts, and triggers.
- 6 Click **Save BOM** — all tabs saved as budget baseline



Product-level BOM

ROLE: CEO / FACTORY SUPERVISOR

- 1 Go to **Projects** → **Products**, click **BOM** on any product
- 2 Add materials specific to this product (Wardrobe, Kitchen, etc.)
- 3 Add labour operations and their costs
- 4 Add product-specific expenses
- 5 Live **Margin** shows: Quoted Price – BOM Cost (CEO/Admin only)
- 6 Click **Save Product BOM**

Note: Margin and quoted price are visible to CEO and Admin only.

2.5 Milestones & Payment Schedule



Milestone Management

ROLE: CEO / ACCOUNTS

Setting Milestones

- 1 Open Project BOM → **Milestones tab**
- 2 Default 30% / 40% / 30% schedule pre-populated
- 3 Edit milestone names as needed
- 4 Enter Amount or % — the other auto-calculates
- 5 Set trigger for each milestone
- 6 Save BOM — milestones are saved simultaneously

Milestone Triggers

Trigger	What activates it
Manual	You click "Mark Ready"
On Delivery	Auto when delivery logged
On Installation	Auto when installation complete
On Handover	Auto when handover signed off
On QC Pass	Auto when QC inspection passes

Once a milestone status becomes **Invoiced** it is locked and cannot be edited or deleted.

2.6 Purchase Orders & Procurement



Raising a Purchase Order

ROLE: PROCUREMENT / CEO

- 1 Go to **Inventory** → **Purchase Orders** → **+ New PO**
- 2 Select **Vendor** from vendor master
- 3 Select **Project** and delivery destination (Warehouse / Site)
- 4 Click **+ Add Item** for each material: name, unit, qty, rate
- 5 Amount auto-calculates per line; total updates live
- 6 Set expected delivery date and any instructions
- 7 Click **Save** — PO code auto-generates (PO/001)
- 8 Preview and print PO using **Preview / Print**
- 9 Change status to **Sent to Vendor** after sharing



Receiving Goods

ROLE: PROCUREMENT / FACTORY SUPERVISOR

- 1 Open the PO (status must be **Sent** or **Partially Received**)
- 2 Click **Receive** on the PO list row
- 3 Enter received quantity per item
- 4 If delivered to **Warehouse**: stock automatically updated
- 5 PO status changes to Partially Received or Fully Received
- 6 Record vendor bill in **Finance** → **Vendor Bills**

Important: All materials must arrive via PO or purchase to update warehouse stock. No ad-hoc stock additions.

2.7 Warehouse & Stock Management



Stock Operations

ROLE: PROCUREMENT / FACTORY SUPERVISOR


Adding Stock

- 1 Receive via PO (preferred) — qty auto-updates
- 2 Or: Manual Purchase → set destination to Warehouse
- 3 Or: Stock Adjustment for corrections

Stock Levels

- 1 Go to **Inventory** → **Warehouse**
- 2 View current qty, unit, rate per item
- 3 Low stock items shown in **Reports** → **Stock Report**
- 4 Reorder when stock falls below safety level

2.8 Material Requests & Issues



Raising a Material Request

ROLE: FACTORY SUPERVISOR

- 1 Go to **Inventory** → **Material Requests** → + **New Request**
- 2 Select Project, Product, and the required Item
- 3 Enter quantity needed and reason
- 4 System checks: Requested qty vs BOM Budget remaining
- 5 If within budget → **Auto-Approved**, issue created instantly
- 6 If over budget → status **Pending**, wait for CEO/Admin approval

Rule: No direct material issue. ALL issues must go through a Material Request first.



Material Returns

ROLE: FACTORY SUPERVISOR

- 1 Go to **Inventory** → **Material Returns** → + **Return**
- 2 Select the original Issue record
- 3 Enter quantity being returned and reason
- 4 Stock automatically added back to warehouse
- 5 Remaining BOM budget qty is recalculated

Returns reduce issued qty and restore remaining budget, allowing future requests against the same BOM budget.

2.9 Manufacturing Jobs & Job Cards



Manufacturing Jobs

ROLE: FACTORY SUPERVISOR

- 1 Go to **Factory / MES** → **Manufacturing Jobs**
- 2 Click **Auto-Create Jobs** to generate one job per product
- 3 Or click + **New Job** to create manually
- 4 Set priority (Normal / High / Urgent) and due date
- 5 Open the job → click **Operations** to add work steps
- 6 Assign each operation to a worker and machine
- 7 Update operation status as work progresses



Job Cards for Workers

ROLE: FACTORY SUPERVISOR

- 1 Go to **Factory / MES** → **Job Cards**
- 2 Filter by worker, status, or work centre
- 3 Each card shows: Product, Operation, Machine, Due Date
- 4 Click **Print for Worker** to print that worker's cards
- 5 Click **Print All** for full factory card set
- 6 Workers update their operation status (In Progress / Done)

Job cards include signature lines for worker acknowledgment.

2.10 Quality Control (QC)



QC Inspection

ROLE: FACTORY SUPERVISOR / CEO

- 1 Go to **Operations** → **QC Inspections**
- 2 Click + **New QC Entry**
- 3 Select Project and Product being inspected
- 4 Record inspection date and inspector name
- 5 Set result: **Pass** or **Fail**
- 6 Add remarks (defects, observations)
- 7 If Pass → product cleared for delivery
- 8 If Fail → return to factory for rework

A QC Pass on a product triggers any milestone set to **On QC Pass**.



QC Reports

ROLE: CEO / FACTORY SUPERVISOR

- 1 Go to **Operations** → **QC** to view all inspections
- 2 Filter by project or status (Pass/Fail)
- 3 Track fail rate per project or product type
- 4 Use data to improve material selection and carpentry SOP

2.11 Site Delivery & Installation



Site Delivery

ROLE: SITE SUPERVISOR

- 1 Go to **Site & Installation** → **Deliveries** → + **New Delivery**
- 2 Select project and list items being delivered
- 3 Record delivery date, vehicle, and driver
- 4 Log client acknowledgment
- 5 Save — any milestone set to **On Delivery** auto-triggers
- 6 Toast notification confirms milestone is "Ready to Invoice"



Installation & Handover

ROLE: SITE SUPERVISOR

- 1 Go to **Site & Installation** → **Installation**
- 2 Create installation record linked to project
- 3 Assign installation team and set dates
- 4 Update status: Scheduled → In Progress → Completed
- 5 Enter handover date on completion
- 6 Milestones for **On Installation** and **On Handover** auto-trigger
- 7 Project status can be changed to **Completed**

2.12 Invoicing & Collections



Raising an Invoice

ROLE: ACCOUNTS / CEO

- 1 Go to **Finance** → **Milestones**
- 2 Find milestone with status **Ready to Invoice**
- 3 Click **Raise Invoice** — invoice modal pre-fills amount & description
- 4 Confirm details and Save — invoice code auto-generates (INV/001)
- 5 Alternatively: go to **Finance** → **Sales Invoices** → + **New Invoice**



Recording Receipts

ROLE: ACCOUNTS / CEO

- 1 Go to **Finance** → **Receipts** → + **Record Receipt**
- 2 Select project and link to invoice
- 3 Enter amount received, date, and mode (NEFT/Cash/Cheque)
- 4 Save — outstanding balance auto-reduces
- 5 View outstanding per project in **Reports** → **Receivables**

6 Share invoice with client

6 Milestone status updates to **Invoiced** once fully received

3. Role & Access Matrix

What each role can see and do in the system

MODULE	CEO	ADMIN	FACTORY SUPERVISOR	SITE SUPERVISOR	ACCOUNTS	SALES	PROCUREMENT
Overview / Dashboard	✓	✓	✓	✓	✓	✓	✓
CRM & Sales (Leads, Quotations)	✓	✓	—	—	—	✓	—
Projects & Products	✓	✓	✓	✓	✓	✓	✓
Operations (Labour, Expenses, QC)	✓	✓	✓	✓	—	—	—
Inventory (Warehouse, MR, Issues)	✓	✓	✓	—	—	—	✓
Purchases & Purchase Orders	✓	✓	✓	—	—	—	✓
Finance (Invoices, Receipts, Bills)	✓	✓	—	—	✓	—	—
Banking & Accounts	✓	✓	—	—	✓	—	—
Reports (P&L, Variance, Receivables)	✓	✓	—	—	✓	✓	—
Site & Installation	✓	✓	—	✓	—	—	—
Factory / MES (Jobs, Cards)	✓	✓	✓	—	—	—	—
HR & Payroll	✓	✓	—	—	—	—	—
Master Data (Items, Vendors, Workers)	✓	✓	✓	—	—	—	✓
User Management	✓	✓	—	—	—	—	—

Restricted Financial Data (CEO & Admin Only)

DATA	VISIBILITY	WHERE RESTRICTED
Gross Margin % per product	CEO & Admin only	Product BOM overlay
Quoted price on BOM	CEO & Admin only	Product BOM overlay
Projected Profit per project	CEO & Admin only	AI assistant, Project detail
P&L Report	CEO & Admin only	Reports → Profit & Loss
Variance Tab	CEO & Admin only	Project BOM → Variance
Business Snapshot (AI)	CEO & Admin only	AI assistant

Landing Page Per Role

ROLE	OPENS AT LOGIN	PRIMARY FOCUS
CEO	CEO Dashboard	Full business overview, all KPIs
Admin	Dashboard	System administration, full access

ROLE	OPENS AT LOGIN	PRIMARY FOCUS
Factory Supervisor	Factory Dashboard	Jobs in progress, material requests
Site Supervisor	Site Dashboard	Deliveries, installations, handovers
Accounts	Sales Invoices	Invoicing, receipts, billing
Sales	Leads & Enquiries	Leads pipeline, quotations
Procurement	Purchases	Purchase orders, warehouse stock

4. Auto-Generated Code Reference

System-generated codes for all records — format and examples

MODULE / RECORD	CODE FORMAT	EXAMPLE	NOTES
Lead / Enquiry	ENQ/001	ENQ/001	Sequential, 3-digit padded
Quotation	STR/Q/001	STR/Q/001	STR = Appletree prefix
Project	P001	P001	Sequentially from P001
Product	P001_001	P001_001	ProjectCode_ProductSeq
Purchase Order	PO/001	PO/001	Sequential, 3-digit padded
Material Request	MRQ/001	MRQ/001	Sequential
Material Issue	ISS/001	ISS/001	Sequential
Material Return	RET/001	RET/001	Sequential
Manufacturing Job	JOB/001	JOB/001	Sequential, 3-digit padded
Sales Invoice	INV/001	INV/001	Sequential
Receipt	REC/001	REC/001	Sequential
Vendor Bill	BILL/001	BILL/001	Sequential
Milestone	MS + UID	MS7f3a...	Auto internal ID
Project Budget	PB + UID	PB9c1d...	Auto internal ID
Warehouse Item	W + UID	Wab12...	Auto internal ID

5. Key Business Rules & Controls

System-enforced rules and important operating guidelines

Material Control Rules

- RULE 1 — No Direct Material Issue:** All material issues must go through a Material Request. No worker or supervisor can take stock directly from the warehouse without raising an MR first.
- RULE 2 — Budget Enforcement:** If the requested quantity exceeds the remaining BOM budget, the request cannot be auto-approved. It must be manually approved by CEO or Admin.
- RULE 3 — Remaining Qty Calculation:** Remaining = BOM Budget Qty – (Total Issued – Total Returned). This is recalculated live on every request.

Financial Controls

- RULE 4 — Margin Confidentiality:** Gross margin %, quoted price, and projected profit are visible only to CEO and Admin. All other roles see cost data but not the profit calculation.
- RULE 5 — Milestone Locking:** Once a milestone is invoiced, it cannot be edited or deleted. This ensures billing history integrity.
- RULE 6 — Purchase to Warehouse:** All material purchases must specify a destination (Warehouse or Site). Warehouse purchases automatically update stock levels.

Process Gates

GATE	CONDITION TO PASS	WHAT HAPPENS
Quotation → Project	Status must be Approved	Convert button appears; one-click creates project
Material Request → Auto-Issue	Requested qty <= remaining BOM budget AND warehouse has stock	Issue created instantly, stock deducted
Milestone → Ready to Invoice	Trigger condition met (delivery logged, installation complete, etc.)	Auto-triggered; "Raise Invoice" button appears
QC Pass → Delivery	QC status = Pass	Product cleared for dispatch; milestone may trigger
Project → Completed	All invoices raised, installations done	Status changed manually to Completed

Naming & Data Conventions

- Project Codes** are permanent once created. Never rename or delete a project code — it links to all products, BOMs, invoices, and material records.
- Warehouse Items** should use consistent naming. The same item with two different names will create duplicate stock entries.
- Vendor Names** must be set up in Master Data → Vendor Master before raising a PO against them.
- Workers** must be set up in Master Data → Workers before being assigned to job operations.

AI Assistant — What It Knows

The built-in AI assistant can answer business questions using live data. Type natural language queries in the chat panel.

QUERY TYPE	EXAMPLE	WHO CAN ASK
Project status	"Show all projects" / "Status of Sharma project"	All roles
Outstanding payments	"How much is outstanding" / "Who hasn't paid"	All roles
Factory status	"What jobs are in progress" / "Factory status"	All roles
Stock & inventory	"What is our stock" / "Low stock items"	All roles
Profit & margin	"What is our profit" / "Show margins"	CEO & Admin only
Business snapshot	"How are we doing" / "Business summary"	CEO & Admin only
Material requests	"Pending MRs" / "Material requests"	All roles
Quotations pipeline	"Show quotations" / "Sales pipeline"	Sales / CEO / Admin