

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center /

Fireblocks Help Center

For Developers

Co-signer management

The Co-signer management tab

Overview

This tab provides a view of your API Co-signers, their current status and health, as well as their associated API users.

This is the first phase of a multi-phase development effort. The Co-signers management tab is a new tab in the Console's Developer center where you can see all Co-signers in your workspace.

Viewing the API Co-signers

In case you currently do not have any Co-signer connected to your workspace, you will encounter a "empty state" window, from which you can select the [Learn about co-signers](#) button for further information.

To view your API Co-signers, in your Console's left-side navigation panel select **Developer center > Co-signers**.

- In the upper left side you can see the **Co-signers** field, which shows within parenthesis the number of API Co-signers in your current workspace, including how many are online and offline.
- In the upper right side you can select the [Learn about co-signers](#) button for further information.
- Within each entry:
 - You can see its unique ID in the title. It is always the same ID, regardless of the workspace the Co-signer is connected to.
 - You can see this Co-signer's associated **Paired API users**, including their names, roles, and associated groups.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

online is indicated.

Learning about a new Co-signer installation

To learn about installing a new API Co-signer in your workspace:

1. Select the **Learn about co-signers** button on the upper-right side of the Co-signer tab.
2. In the **About co-signer** window, you can read about the Co-signer characteristics in the **What is a co-signer** sub-section, and about adding a new Co-signer in the **How do I add a co-signer to the workspace** subsection.
3. Under the **How do I install a co-signer** sub-section, select **Manual** in order to manually configure the Co-signer. Selecting either the Azure SGX or AWS Nitro type options leads you to Help Center setup instructions.
4. Alternatively, selecting the **Quick** option under the **How do I install a co-signer** allows you to select the Azure SGX, which leads you to the Microsoft Azure portal for the SGX quick installation wizard.

Related API User actions

Since the API users tab is logically connected to the Co-signers management tab, deleting a user **which is paired with a Co-signer** also removes it as a Co-signer:

- When attempting to delete a signer/admin user which is paired to a Co-signer, you will be prompted with the following confirmation notice: "The user will no longer be able to access the workspace and their signing keys will be deleted."
- If you delete the last remaining API user associated with a particular Co-signer, you will be prompted with the following confirmation notice: "This is the last API user in the Co-signer. Deleting the user will also delete the Co-signer from the workspace."

Renaming a Co-signer

To rename your Co-signer:

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

Note:

You **cannot rename the Fireblocks Communal Test Co-signer**, as it is constant, and does not have the rename option enabled (the action menu is absent).

Add Co-signer

Minimum supported API Co-signer and Fireblocks Mobile App versions:

- SGX: 3.7.1
- Nitro: 2.0.5
- GCP: 0.9.5
- Fireblocks's Mobile App: 2.11

To add a new Co-signer:

1. Navigate to your **Console's left panel > Developer's portal > Co-signers**.
2. Select **+ Add co-signer** to open a wizard which will guide you through connecting a Co-signer to the workspace. You can connect a new Co-signer or an existing one that is connected to a different workspace.
3. In the *Add co-signer* modal, under the *Co-signer name* field, enter your Co-signer's name.
4. If you are installing a new Co-signer, select **Install a new co-signer on the local machine**, select **Continue** and then:
 - a. In the *Add co-signer* modal, select an available unpaired API user from the drop-down list, then select **Add**. This action creates a new entry in the Co-signers tab. You will use it to connect the Co-signer you plan to install using the API user you selected.
 - b. Under the newly-created Co-signer entry, select **Pair API user** to get the pairing token for the API user.
 - c. In the *Pair the API user with the Co-signer* modal, select one of two options: **Manual** to copy the download link for the Co-signer installation script based on the type, or **Quick** to install a Co-signer using one of the listed cloud service provider's automated processes.
 - d. Select **Copy pairing token** to copy it to your clipboard, so you can use it during the Co-signer's installation process.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Fireblocks Help C

/

only, the version information of the latest Co-signer version, the Co-signer type and version information will appear in the Co-signers tab. Additionally, management operations will become available.

5. If you want to connect an existing Co-signer to the workspace, select **Use an existing co-signer from another workspace**, select **Continue** and then:
 - a. In the *Add co-signer* modal, select an available unpaired API user, then select **Add**. This action creates a new entry in the Co-signers tab. You can use it to connect the Co-signer to the workspace using the API user you selected.
 - b. Under the newly created Co-signer entry, select **Pair API user** to get the pairing token for the API user.
 - c. Run the `./cosigner add-user` command on the local machine where your existing Co-signer is running.
 - d. In the *Pair the API user with the Co-signer* modal, select **Copy pairing token** to copy and paste it when prompted.

Pair API user

To pair the API user with the Co-signer:

- a. Navigate to your **Console's left panel > Developer's portal > Co-signers**.
- b. Expand your desired Co-signer, then select **Pair API user**.
- c. In the *Pair API user* modal, select an available API user. You may also select and configure the **Set callback handler**, which is used for approving, rejecting or ignoring transactions and workspace changes. Select **Pair**.
- d. Once the new API user is successfully paired, API users with the Signer or Admin roles require the Owner's approval for MPC signing keys.
- e. Once the Owner approves the MPC signing keys for the API user, the pairing process is complete.

Note:

Outdated Co-signers do not display the type and version information available in the latest Co-signer versions.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Fireblocks Help C

/

- Navigate to your **Console's left panel > Developer's portal > Co-signers**.
- Expand your desired Co-signer, then select the three dots next to the API user you want to unpair from this Co-signer.
- Select **Unpair** from the menu.

Notes:

- Unpairing the last remaining API user removes the Co-signer from your Console. Although the Co-signer instance still continues to run, it is no longer accessible via the Console or APIs.
- To re-connect that Co-signer to your workspace, follow the **Add Co-signer steps above**, select **Use an existing Co-signer** and pair an available (unpaired) API user to it.

Configure the Callback Handler

To configure the Callback Handler:

- Navigate to your **Console's left panel > Developer's portal > Co-signers**.
- Expand your desired Co-signer, and under the Callback Handler column, select the **+ sign**.
- Select **Configure Callback Handler** from the menu.
- Enter the appropriate parameters for your Callback Handler in the URL and Authentication fields. For more details, see [here](#). Select **Update**.

Note: the options to configure the Callback Handler and pair additional API users are not enabled for outdated Co-signers (see versions list above).

Pair API user to the Fireblocks Communal Test Co-signer

As you add a new API user via the "Add API User" modal, you have the option to connect the newly created API user directly to the Fireblocks Communal Test Co-signer. Select **Pair**

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Viewing the API Co-signers

Learning about a new Co-signer installation

Related API User actions

Renaming a Co-signer

Add Co-signer

Pair API user

Unpair API user

Configure the Callback Handler

Pair API user to the Fireblocks Communal Test Co-signer



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)