

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Bybit account

Updated 8 months ago

Configuring your Bybit account

To configure your Bybit account to connect to Fireblocks:

1. Refer to the [Bybit.com API Documentation](#) to learn how to generate an API key.
2. Name your new API Key "Fireblocks" when prompted
3. Enable the following permissions:
 - **Read-Write**
 - **Only IPs with permissions granted are allowed to access the OpenAPI** (optional)
 - **Assets**
 - **Account Transfer**
 - **Subaccount Transfer**
 - **Withdrawal**
4. Copy and securely save the API Key and API Secret. You will need them when adding this exchange to your workspace.
5. If you enabled IP restriction above, enter the following Fireblocks IP address:
52.76.208.129. Bybit API Keys without IP whitelisting expire after 90 days.

Note

Configuring a Bybit Off Exchange account requires a separate process. After signing a Fireblocks Off Exchange agreement, Bybit sends an email containing your new Bybit UID. Use this UID to create a new API key and designate it the "Fireblocks Binding Key." This key is required to connect Bybit Off Exchange to your Fireblocks workspace. [Learn more about Fireblocks Off Exchange](#).

Configuring Fireblocks

1. In the Fireblocks Console, go to **Accounts > Connected accounts**.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Fireblocks Help Center

/

- b. **API Key**: Enter the API Key that you saved from Bybit.
- c. **API Secret**: Enter the Secret key that you saved from Bybit.
- d. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Bybit account appears on the Exchanges page, with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault accounts, whitelisted addresses, Fireblocks P2P Network connections, and other connected exchange accounts to your Bybit account.

Enabling withdrawals from Bybit

You can transfer assets to your Bybit account from vault accounts, other exchanges, and Fireblocks P2P Network members. To withdraw from your Bybit account to any destination in Fireblocks, add the deposit address to your Bybit Wallet Address Book. [Learn more about managing your Bybit Address Book in the Bybit help center.](#) [Learn more about enabling exchange account withdrawals in Fireblocks.](#)

Important

Bybit refers to the main account as the Funding account. To withdraw funds from a Bybit sub-account, transfer them to the Funding account first.

Bybit sub-accounts

[Learn more about connecting a Bybit sub-account.](#)

Was this article helpful?

Yes

No

Don't see what you're looking for? Log in for the full Help Center experience

Ending withdrawals from Bybit

Bybit sub-accounts

Related Articles

 Bybit sub-account