

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Enable or disable Gas Station auto-fueling

Updated 3 days ago

Newer workspaces use Gas Station 2.0

If your workspace was created in January 2024 or later, refer to the [Gas Station 2.0 setup documentation](#).

Vault account auto-fueling is always available for API users with the Gas Station enabled, and any vault account with the Gas Station badge in the Console participates in the Gas Station service.

- When an incoming token transaction to an auto-fueling vault account completes, Fireblocks automatically transfers the appropriate base asset from the Gas Station to the vault account.
- When an outgoing transaction from an auto-fueling vault account completes, Fireblocks checks the token and gas balances. The vault account will be refueled if the token balance is above 0.00001 and the base asset is below the set threshold. Token transfers from this vault account to any destination will then have sufficient gas to cover transaction fees.

Enabling auto-fueling in the Console

For new vault accounts, simply select **Auto-fuel with gas after an incoming transaction completes** when you [create the account](#).

For existing vault accounts, go to **Accounts**, find the appropriate vault account, and then select **More Actions (...)** > **Enable Auto-Fueling** > **Enable**. The Gas Station badge appears next to the name of the vault account when you're done.

Enabling auto-fueling via the API

For new vault accounts, call the [Create a new vault account](#) endpoint and set the **autoFuel** field to **true**.

For existing vault accounts:

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

In the Fireblocks Console, go to **Accounts**, find the appropriate vault account, and then select **More Actions (...)** > **Disable Auto-Fueling** > **Disable**. The Gas Station badge is removed when you're done.

Disabling auto-fueling via the API

1. Call the [Get vault accounts \(Paginated\)](#) endpoint to find the vault account's ID.
2. Call the [Set auto-fueling to on or off](#) endpoint, enter the vault account's ID in the **vaultAccountId** field, and then set the **autoFuel** field to **false**.

Was this article helpful?

Yes

No

Related Articles

-  Set Up the Gas Station
-  My Gas Station is configured properly but a transfer failed due to insufficient funds for fees
-  General troubleshooting for the Gas Station
-  About the Gas Station
-  Enable the Gas Station
-  Default Gas Station values
-  Setup for Gas Station 2.0
-  Configure Gas Station settings
-  About the Fireblocks Gasless Service
-  Gas Station Autoboot
-  View vault accounts with auto-fueling enabled
-  Fund the Gas Station

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

[info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)