

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center /

Using the Fireblocks Gasless Relay

Updated 2 months ago

Premium feature

This is a premium feature that requires additional purchase and enablement by Fireblocks Support. If you're interested in this feature for your workspace, contact your Customer Success Manager.

Alternatively, if you want to experiment with the Fireblocks Gasless Relay on testnet implementations, contact your Customer Success Manager to discuss enabling a 30-day testing period for your workspace.

What is Fireblocks Gasless Relay?

Fireblocks Gasless Relay is a plug-and-play service that eliminates the operational burden of managing gas fees for your blockchain transactions. Instead of maintaining multiple gas wallets, monitoring balances, and constantly topping up accounts across different networks, Fireblocks handles all gas payments on your behalf through a managed relay service.

With Gasless Relay, you can send tokens and execute transactions without needing native blockchain tokens for gas fees. Fireblocks pays the gas upfront, and you receive a consolidated invoice at the end of each month.

How it works

1. You configure the feature in your workspace settings (explained below)
2. You initiate transactions from your workspace as usual
3. Fireblocks pays the gas through our managed relay infrastructure
4. Your transactions execute seamlessly across supported networks
5. You receive a monthly invoice for actual gas costs plus any applicable subscription fee

Gasless Relay does not support auto-boosting for stuck transactions

The Fireblocks Gasless Relay does not automatically handle stuck transactions. If a transaction becomes stuck, you must manually [boost it using the Replace-by-Fee \(RBF\)](#)

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

- All **EVM-compatible blockchains**, including Ethereum, Polygon, Arbitrum, Optimism, and more
- All tokens on these supported networks

Support for select non-EVM networks may be available

Support for select non-EVM networks (including specific USDC operations) may be available. [Contact your Customer Success Manager](#) for details on additional network capabilities.

How to connect to the Fireblocks Gasless Relay

1. In the Fireblocks Console, go to **Settings**  > **General** > **Gasless transactions**.
2. Toggle on **EVM**.
3. On the EVM window, select **Fireblocks** as the relay type.
4. Select **Save**.
5. [Submit a request to Fireblocks Support](#) to get the Fireblocks Gasless Relay enabled in your workspace.
6. Your Fireblocks CSM will follow up with you to determine which blockchains you need gasless support for, your estimated monthly transaction volume, and your specific use cases and requirements.
7. After you sign the service agreement, Support will enable the Gasless Relay in your workspace, and you can start transacting.

Was this article helpful?

Yes

No

ON THIS PAGE

What is Fireblocks Gasless Relay?

How to connect to the Fireblocks Gasless Relay

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center



-  Gasless settings for individual transfers
-  Gasless fee contingencies
-  Configuring Solana Gasless transactions
-  About the Fireblocks Gasless Service
-  Using an external workspace as a gasless relay



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)