

Don't see what you're looking for? Log in for the full Help Center experience

Binance.US account

Updated 4 months ago

Configuring your Binance.us account

To configure your Binance.us account to connect to Fireblocks:

1. Refer to the [Binance.us API Documentation](#) to learn how to generate a Binance.us API key.
2. When prompted to do so, name your new API Key "Fireblocks."
3. After you confirm the validity of your new API key, copy and keep a record of both the API Key and Secret Key. You will need them when adding this exchange to your workspace.
4. Make sure you enable the following API Restrictions:
 - **Reading**
 - **Withdrawals**
5. If you intend to add trading account support to this account, also enable these:
 - a. **Spot & Margin Trading**
 - b. **Futures**
 - c. **Margin**
6. Under IP access restrictions, select **Restrict access to trusted IPs only**, delete the 0.0.0.0 address, and then add the following IP addresses:
 - 40.87.67.58
 - 40.117.39.160

Configuring Fireblocks

1. In the Fireblocks Console, go to **Accounts > Connected accounts**.
2. Select **+ Connect Account**.
3. Select **Binance.us**, select **Main Account**, and then complete the following fields:
 - a. **Name on Fireblocks:** Enter the name you want to give this exchange account on Fireblocks.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

4. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Binance.us account appears on the Exchanges page along with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault accounts, whitelisted addresses, Fireblocks P2P Network connections, and other connected exchange accounts to your Binance.us account.

Binance sub-account transfers

Fireblocks supports direct transfers between Binance sub-accounts that belong to the same Binance main account.

These transfers are performed off-chain, using Binance's internal transfer mechanism. Assets are moved within Binance's infrastructure and are not recorded as blockchain transactions.

This enhancement removes the need to route funds through the main account when transferring assets between sub-accounts.

Enabling withdrawals from Binance.us

[Learn more about enabling exchange account withdrawals in Fireblocks.](#)

Binance.US sub-accounts

[Learn more about connecting a Binance.US sub-account.](#)

Was this article helpful?

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



Configuring your Binance.us account

Configuring Fireblocks

Binance sub-account transfers

Enabling withdrawals from Binance.us

Binance.US sub-accounts

Related Articles



Binance.US sub-account



Binance account



Binance sub-account



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)