

Don't see what you're looking for? Log in for the full Help Center experience

Bitstamp sub-account

Updated 1 year ago

Overview

Fireblocks supports Bitstamp sub-accounts via exchange connectivity. Connect the exchange, and rebalance securely between your exchange's main account and sub-accounts on Fireblocks.

Important:

- If you already have a Bitstamp sub-account connected to this workspace, you must remove it and then reconnect it.
- If you have a Bitstamp main account connected, you may need to remove it if the email field was left blank.

Configuring your Bitstamp sub-account

To configure your Bitstamp sub-account to connect to Fireblocks:

1. Refer to the [Bitstamp API Documentation](#) for instructions on how to create a sub-account.
2. Copy and keep a record of both the API Key and API Secret. You will need them when adding this exchange to your workspace.
3. Make sure you enable the following options:
 - Withdrawals
 - a. If you want to allow fiat transfers as [described above in the main account section](#), enable **Open**, **cancel** and **view bank withdrawals**.
 - b. **Create crypto withdrawals**
 - **Allow for all current and future available assets**
 - c. **List withdrawal requests**
 - General permissions

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

4. In case you want to enable fiat transfers between Bitstamp and conventional bank accounts, [contact Fireblocks Support](#) to activate this feature and then take the following steps:
 - Confirm that **Bank** permissions are enabled.
 - On the Bitstamp deposit page, locate the **Bitstamp Account Number** and **Bitstamp Deposit Reference** and copy them. You will need them when configuring this feature on your workspace.
5. After you confirm the validity of your new API key, copy and keep a record of both the API Key and Secret Key. You will need them when adding this exchange to your workspace.
6. Find the **Client ID** by navigating to **My information** under the user/account logo on the top right corner.
7. Copy the **Client ID**. You will need it when adding this exchange to your workspace.

Configuring Fireblocks

1. In the Fireblocks Console, go to **My Funds > Accounts > Exchanges**.
2. Select **+ Exchange Account**.
3. Select **Bitstamp**, select **Sub account**, and then complete the following fields:
 - **Display Name:** Enter the name you want to give this exchange sub-account in your workspace.
 - Under **Link to Main Account**, select the main account you want to connect to this sub-account. Remember, your main account must be connected to Fireblocks *before* you can connect a sub-account.
 - **API Key:** Enter the API key that you saved from Bitstamp.
 - **Secret:** Enter the API Secret that you saved from Bitstamp.
 - **Customer ID:** Enter your customer ID on Bitstamp.
 - **Sub-account unique identifier:** Select and enter a unique sub-account identifying number.
4. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Configuring your Bitstamp sub-account

Configuring Fireblocks

Related Articles

-  Bybit sub-account
-  Coinbase Pro and Coinbase Exchange sub-accounts
-  Crypto.com sub-account
-  Coinhako sub-account
-  Bitstamp account
-  Deribit sub-account
-  Gate.io sub-account
-  HTX (formerly Huobi) sub-account
-  Bitget sub-account
-  Binance.US sub-account
-  Binance sub-account
-  Bitfinex sub-account
-  Kraken, Kraken Futures and Kraken International sub-accounts
-  KuCoin sub-account
-  OKX (OKEx) - API V5 sub-account

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)