

Don't see what you're looking for? Log in for the full Help Center experience

Bybit sub-account

Updated 8 months ago

Overview

Fireblocks supports Bybit sub-accounts via exchange connectivity. Connect your accounts and rebalance securely between your exchange's main account and sub-accounts on Fireblocks. Your Bybit main account must be fully configured in your Fireblocks workspace before connecting a sub-account. Attempting to connect a Bybit sub-account using the main account connection dialog in the Fireblocks Console will be unsuccessful.

Important

Changes in your Policies might be required to support sub-account transfers.

Configuring your Bybit sub-accounts

To configure your Bybit sub-account to connect to Fireblocks:

1. Refer to the [Bybit.com API Documentation](#) for instructions on how to create a sub-account.
2. When prompted to do so, name your new API Key "Fireblocks."
3. Whitelist the following (optional) Fireblocks IP address or IP segment:
52.76.208.129.
4. Copy and keep a record of both the API Key and API Secret. You will need them when adding this exchange to your workspace.

Configuring Fireblocks

1. In the Fireblocks Console, go to **Accounts > Exchanges**.
2. Select **+ Connect Account**.
3. Select Bybit, select the **Sub-account** tab, and then follow these steps:

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

- c. **API Key**: Enter the unique sub-account API key that you saved from Bybit.
- d. **API Secret**: Enter the unique sub-account API secret that you saved from Bybit.
- e. **UID**: Enter the unique User ID that you saved from Bybit.
- f. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Bybit sub-account appears on the Exchanges page along with all managed assets and their balances. Following Admin Quorum approval, transfers will be available between this sub-account and its Bybit main account.

Withdrawing from Bybit sub-accounts

Bybit refers to the main account as the Funding account. To withdraw funds from the connected exchange sub-accounts, transfer them to the Funding account first.

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Configuring your Bybit sub-accounts

Configuring Fireblocks

Withdrawing from Bybit sub-accounts

Related Articles



Bitstamp sub-account

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

-  Deribit sub-account
-  Gate.io sub-account
-  HTX (formerly Huobi) sub-account
-  Bitget sub-account
-  Binance.US sub-account
-  Binance sub-account
-  Bitfinex sub-account
-  Kraken, Kraken Futures and Kraken International sub-accounts
-  KuCoin sub-account
-  Bybit account
-  OKX (OKEx) - API V5 sub-account



fireblocks.com

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)