

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Supported exchanges & assets for Off Exchange

Updated 3 months ago

Overview

Supported exchanges

We support the following exchanges for the Fireblocks Off Exchange feature.

Exchange	
Deribit	Available
ByBit	Available
HTX	Early Access
Gate	Available

Supported assets

Not all assets supported by an exchange can be accepted by the exchange as collateral. In the exchange sections below, you can find the assets supported as collateral by each exchange.

If you accidentally send unsupported assets to your CVA:

- The exchange should not credit you for these assets.
- You should be able to withdraw these assets from your CVA. If removing the collateral fails, you must ask the exchange's support team to confirm the collateral removal request.
- Contact [Fireblocks Support](#) if needed.

Settlements

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

- **Settlement cycles:** Each exchange defines the duration and timing of each settlement cycle. Additionally, an exchange can determine whether you are allowed to request ad-hoc settlements.
- **Settlement approval SLA time:** The time provided to you for reviewing and approving/signing settlement transactions before they are sent to the exchange for auto-approval by the collateral signer.
- **Settlement review SLA time:** The time provided to you to manage a dispute in case of rejection/failure before the transaction is sent for forced settlement by the exchange's collateral signer.

Settlement threshold

A settlement threshold is the minimal amount above which a settlement request is sent. Any balance under that threshold does not warrant settlement.

Deribit Off-Exchange parameters

Account connection

Credit limits

Supported assets

Settlements

Supported account types

The Deribit Main account can be set up for off-exchange. Balance calculation for settlements will include all the Main account's sub-accounts. The user should configure the sub-accounts on the Fireblocks exchange connection to see the distribution of assets between the main and sub-accounts.

There is no limitation on the types of products available when using the Fireblocks off-exchange settlement. However, negative balances of any currency are restricted when using the cross-collateral margin mode. When a currency balance goes negative, we execute a cash rebalancing spot trade to cover the shortfall from another available currency. This limitation will be addressed towards the end of Q1 2025 to allow clients to take full advantage of the cross-collateral margin mode.

Don't see what you're looking for? Log in for the full Help Center experience

To establish the exchange connection on Fireblocks, the API key created on Deribit should have the following scopes:

- **Account:** Read/Write
- **Wallet:** Read/Write
- **Custody:** Read/Write

For the 2FA configuration, the long alphanumeric code above the QR code on Deribit’s UI should be used instead of the 6-digit 2FA code. This code is visible only at the time of creation and cannot be retrieved later on.

Exchange balance reflection

The Fireblocks UI has three columns:

- **Available amount:** The balance available for opening new positions/withdrawable
- **Collateral amount:** The CVA on-chain balance
- **Credit amount:** The mirrored amount on Deribit from the collateral in the CVA

Bybit Off-Exchange parameters

Account connection
Credit limits
Supported assets
Settlements
Supported account types Dedicated customized UTA 2.0 accounts are used for Off Exchange. To open an Off Exchange account, contact your Bybit CSM and provide a new email address to register. Account Level integration

Don't see what you're looking for? Log in for the full Help Center experience

Not applicable.

Exchange balance reflection

- **Available amount:** The transferable amount in Bybit's main account
- **Collateral amount:** The on-chain CVA balance
- **Credit amount:** The total wallet balance of the master and sub-accounts in Bybit

HTX Off-Exchange parameters

Account connection
Credit limits
Supported assets
Settlements
• Supported account types: Spot, Futures, Margin • Account Level integration: Main account • API User configuration:See the HTX API documentation on creating a sub-account. • Exchange balance reflection: Spot, futures, and margin account balances are displayed.

Gate Off-Exchange parameters

Account connection
Credit limits
Supported assets

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

Supported account types

Gate supports Unified (Multi-currency trading) accounts, which allow trading across spot, futures, and margin from a single account.

Account level integration

The connection must be established with Gate's main account.

Sub-accounts are supported and can be configured after the main account is connected.

Specific API user configuration

To establish the exchange connection on Fireblocks, the API key created on Gate must have the following Read/Write permissions:

- Spot Trade
- Perpetual Futures
- Delivery Futures
- Wallet
- Custody
- Withdraw
- Broker
- Option
- Commission Details
- Margin Trading (Unified Account)
- Loan

To create an API key, go [here](#).

During the connection process, collateral signer pairing is required.

Exchange balance reflection

The Fireblocks UI displays three columns:

- **Available amount:** Gate's transferable amount
- **Collateral amount:** The on-chain CVA balance (including Gate's settlement margin requirement)
- **Credit amount:** The total wallet balance across Gate's main account and sub-accounts

Don't see what you're looking for? Log in for the full Help Center experience

ON THIS PAGE

- Overview
 - Deribit Off-Exchange parameters
 - Bybit Off-Exchange parameters
 - HTX Off-Exchange parameters
 - Gate Off-Exchange parameters

Related Articles

-  What happens if Fireblocks or Fireblocks Off Exchange is unresponsive?
-  CoinCover for Off-Exchange
-  Fireblocks Off Exchange FAQ
-  What happens if the exchange defaults or is unresponsive?