

XVatsim

Q8 Pilot Showcase Build - Windows / X-Plane 12 / xPilot

XVatsim is an xPilot companion, not an xPilot replacement. It gives the pilot a cleaner, route-aware VATSIM frequency display inside X-Plane and keeps the frequency story focused on what matters now.

AWAKE



The active card shows route-relevant controllers, COM status, and the current stage of flight without xPilot-style clutter.

SLEEP



When nothing route-relevant needs pilot attention, the display can sleep and remain tucked into its shell.

Install

1. Close X-Plane.
2. Open your X-Plane 12 folder.
3. Copy the included `Resources` folder into the X-Plane 12 root folder.
4. Confirm the plugin exists at `X-Plane 12\Resources\plugins\XVatsim\win_x64\XVatsim.xpl`.
5. Start X-Plane, then connect xPilot to VATSIM.

What To Expect

Departure

- Shows departure airport local services only.
- Keeps CTAF or UNICOM fallback available.
- Can preload COM1 standby with the next recommended controller when Standby Assist is enabled.

Enroute

- Follows the filed VATSIM route using route-sector geometry.
- Shows route-relevant Center controllers only.
- Suppresses offline clutter from the pilot-facing board while preserving log diagnostics.

Arrival

- Wakes at 200nm from destination.

UI Details

- Shows destination-relevant approach, tower, ground, ATIS, CTAF, and route Center status.
- Uses `NO CTAF / UNICOM 122.800` when no CTAF is published.
- TX, RX, COM1, COM2, and MODE C are shown directly in the overlay.
- The shell wakes and sleeps with a projector-style roll animation and sound.
- Display position, scale, and mode persist across simulator restarts.

Menu Controls

- `XVatsim > Open Display` : manually show the overlay.
- `XVatsim > Close Display` : manually hide the overlay.
- `XVatsim > Auto Display` : return to automatic behavior.
- `XVatsim > Standby Assist On / Off` : enable or disable COM1 standby assist.
- `XVatsim > Reset XVatsim Session` : reset the brain and modules as if starting fresh.

Showcase Scope

- Windows only.
- X-Plane 12 only.
- xPilot required.
- IFR flight-plan workflow only for this showcase preview.

Recommended Demo Paths

- **Heavy domestic ATC:** KSAN to KOAK
- **Europe:** EGLL to EHAM or EGLL to LTFM
- **Date line / long-haul:** PHNL to PGUM

If Reporting An Issue

- Include departure and arrival airports.
- Include callsign and whether a VATSIM flight plan was filed.
- Include what xPilot showed and what XVatsim showed.
- Include screenshots and `X-Plane Log.txt` when possible.

Build: XVatsim 0.1.0-preview4 - 2026-04-27