

T S T R A C K E R

PT3 Song Editor

Compose and edit AY chip-tunes on your own machine

For the Timex Sinclair 2068

Written by
David Anderson

Plays PT2 and PT3 tunes via the PTxPlay (Bulba) driver
Companion to the TS Tracker Player

64K SOFTWARE

© 2026

TABLE OF CONTENTS

1	Welcome	3
2	Loading the program	3
3	The first screen	3
4	Scanning a tape	4
5	The song information screen	4
6	The pattern editor	4
6.1	Moving around	5
6.2	Entering notes	5
6.3	Setting volumes	6
7	Hearing your work	6
8	Saving to tape	7
9	The help screen	7
10	Quick key reference	7
11	Limits and notes	8
12	Credits	8

Keep this manual by the keyboard until the key layout is in your fingers.

1. Welcome

TS Tracker turns your Timex Sinclair 2068 into a three-voice music workstation. You can load an existing **PT3** tune from tape and rework it, or start a brand new song from nothing and build it up note by note - no tape required to begin. When you are happy with the result, TS Tracker writes it back out to cassette as a standard song file that the TS Tracker Player (or any PT3 player) can load and play.

The program drives the AY-3-8912 sound chip through the well-known PTxPlay (Bulba) driver, the same engine used by the player, so what you hear while editing is what you will hear on playback.

If you are the sort of person who reads the whole manual before touching the keyboard, good for you - but you needn't. TS Tracker leads you by the hand with on-screen menus and a built-in help page (press **H** any time you are editing). The rest of this booklet fills in the details.

2. Loading the program

TS Tracker is supplied as a **.tap** cassette image. Load it the usual way:

LOAD ""

then start the tape. After a few seconds the **title screen** appears:

```
TS Tracker
PT3 song editor for the TS-2068
a 64K Software production
Press any key to start.

Press any key to continue to the first menu.
```

3. The first screen

When the program starts it has no song in memory, so it shows the **No tape loaded** menu with three choices:

<u>Key Action</u>	
S	Scan tape for songs to edit
N	New song - start composing with no tape needed
Q	Quit back to BASIC

If you just want to make a tune from scratch, press **N** and skip ahead to *The pattern editor*. To work on a song already on cassette, read on.

4. Scanning a tape

Press **S** (or **SPACE**) and start your song tape playing. TS Tracker reads through the tape and lists every song file it finds, up to nine at a time:

```
1 (PT3) MY TUNE
2 (PT3) DEMO SONG
3 (PT2) OLD FAVOURITE
```

Each entry shows its slot number, its format, and its name. When the last song has gone by, press **CAPS SHIFT + SPACE** to stop scanning.

From the directory:

	<u>Key</u>	<u>Action</u>
	1..9	Choose a song to load and edit
	R	Re-scan the tape
	Q	Quit

Pick a number and TS Tracker loads that song into memory.

Note: TS Tracker can *edit* PT3 songs. PT2 songs can be loaded and played, but not edited in this version – the editor will tell you so if you try.

5. The song information screen

Whether you loaded a song or started a new one, you arrive at the **Song info** screen. It shows the tune's vital statistics:

	<u>Field</u>	<u>Meaning</u>
File		The song's name
Type		PT3 (or PT2)
Speed		Playback speed value
Positions		Length of the song, and its loop point
Patterns		How many patterns the song uses

From here press **V** to open the pattern editor, or **Q** to go back.

6. The pattern editor

This is where the work happens. A *pattern* is a short block of up to 64 **rows**, and each row holds one event for each of the three sound channels

(A, B and C). A song plays its patterns one after another in the order set by its position list.

The editor shows sixteen rows at a time:

```
Pat 00/00 Row 00 Ch:A Oct:4
RR  ChA s   ChB s   ChC s
00  C-4 .   --- .   --- .
01  --- .   --- .   --- .
02  --- .   --- .   --- .
...
```

- The line at the top tells you the current **pattern number**, the **cursor row**, the active **channel**, and the current **octave**.
- Each channel cell shows a **note** and a **sample** number. --- means “nothing here”; -- is a **rest** (stop sounding); C-4 is the note C in octave 4.
- Every fourth row is tinted **cyan** and every sixteenth **yellow**, so you can find the beat at a glance, like the bar lines on sheet music.
- The cursor highlights one cell. The right-hand **s** column shows that cell’s sample.

At the bottom, **Free: NNNNN bytes** tells you how much room is left for the song when it is saved.

6.1 Moving around

Key Moves

CAPS SHIFT + 7 / 6	Up / down a row
CAPS SHIFT + 5 / 8	Left / right between channels A, B, C
R	Jump to row 0 (top of the pattern)
O / P	Previous / next pattern
F	Jump to a <u>pattern</u> by number (type two hex digits)

A joystick works for up/down/left/right as well.

Your edits are never lost. Unlike many trackers, TS Tracker keeps the whole song decoded in memory while you work. Moving between patterns, playing the song, and saving all happen automatically – there is no separate “commit” step to remember. Just edit and go.

6.2 Entering notes

TS Tracker lays a piano keyboard across two rows of keys. The bottom row gives the natural notes; the row above gives the sharps:

```
sharps:   D   G       J
notes:   Z X C V B N M
         C D E F G A B
```

Key	Note	Key	Note
	Z C	V F	
	X D	B G	
	C E	N A	
		M B	
	D D#	J A#	
	G F#		

Press a note key to place that note in the cell under the cursor. The note sounds briefly through the AY so you can hear what you picked.

The note's **octave** is set by the number keys 1 to 8. Choose an octave first, then play notes; pressing a number while the cursor sits on an existing note re-tunes that note to the new octave.

Two sharps, **C#** and **G#**, share their keys with the Save (S) and Help (H) commands, so they cannot be typed directly in this version.

Other note-entry keys:

	Key	Action
ENTER		Place a rest (==) - silences the channel from here
SPACE		Clear the cell back to empty (---)
I		Insert a blank row, pushing later rows down
CAPS SHIFT + O		Delete the row, pulling later rows up
9		Clear the whole channel (asks Y/N first)

6.3 Setting volumes

Each cell can carry its own volume. Press U to switch the editor into **volume mode** - the indicator at the top changes from **Oct:** to **Vol:**. Now the keys O to F set the volume (O = silent, F = loudest) of the cell under the cursor. Press U again to return to note mode.

7. Hearing your work

You don't need to leave the editor to listen:

	Key	Action
A		Play the whole song from the current pattern
L		Loop the current pattern over and over

Either way, press any key to stop and return to editing. TS Tracker rebuilds the tune from your edits before it plays, so you always hear the latest version.

8. Saving to tape

Press **S** to save. TS Tracker first rebuilds your song into a proper PT3 file, then asks for a name:

```
Filename (max 8 chars).
Letters / digits / space.
  MY TUNE  01
Bytes:    234
```

Type up to eight characters. TS Tracker adds a two-digit version number automatically and bumps it on every save, so MY TUNE 01, MY TUNE 02, and so on never overwrite each other on the tape.

<u>Key Action</u>	
DEL (CAPS SHIFT + 0)	Erase the last character
ENTER	Start recording - have the tape ready first!
Q	Cancel

Start your recorder, press ENTER, and the song is written as a standard CODE block. Load it back with the TS Tracker Player, or scan it straight back into the editor.

If the song has grown too large to fit the cassette buffer, TS Tracker refuses to save and tells you so. Remove some notes or patterns and try again.

9. The help screen

Press **H** at any time in the editor for a full one-screen key reference. Press any key to return exactly where you left off.

10. Quick key reference

First screen: **S** scan, **N** new song, **Q** quit.

Directory: 1-9 choose, **R** re-scan, **Q** quit.

Song info: **V** edit patterns, **Q** back.

Pattern editor:

Key	Action	Key	Action
CAPS+5/6/7/8	Move cursor	Z..M	Play notes

Key	Action	Key	Action
O / P	Prev / next pattern	1..8	Octave
F	Jump to pattern	ENTER	Rest
R	Jump to row 0	SPACE	Clear cell
A	Play song	I	Insert row
L	Loop pattern	CAPS+O	Delete row
U	Volume mode	9	Clear channel
S	Save to tape	H	Help
Q	Back to song info		

11. Limits and notes

- A song may use up to 14 patterns.
- When you save, the whole tune must fit the cassette song area (about 6.4 K). The Free counter warns you as you approach the limit.
- TS Tracker edits PT3 songs. PT2 songs play but cannot be edited.
- An empty first row on a sounding channel is saved as a rest - silence at the start of the pattern - because the PT3 format always reads row zero.
- Instrument definitions (samples and ornaments) from a loaded song are preserved unchanged; this version edits notes, volumes and arrangement, not the instruments themselves.

12. Credits

TS Tracker is a 64K Software production for the Timex Sinclair 2068. It uses the PTxPlay (Bulba) AY replay driver, shared with the TS Tracker Player. The display style follows the period TS2068 convention of the TIMEX banner, status bar and inverse-video hot-keys.

Happy composing.