
Role/Phase
Phase 1
Authentication
Phase 2
Towing arrangement & Tow Pass assignment
Phase 3
Vehicle arrive and towing
Phase 5
Depollution
Phase 6
Transfer to dismantling
Phase 7
Body Dismantling
Phase 8
Transfer to excavator
Phase 9
Excavator processing
Overseer
Admin
Guard
Forklift Driver
General Worker
Dismantling Supervisor
Excavator Driver
System Behavior
LOGIN
DASHBOARD to show vehicle in each facility
(use to see the rest amount of vehicle in each facility to alert in case of exceeding facility capacity - OPTIONAL)
FACILITY CAPACITY OKTA?
NO
YES
System Alert in the main dashboard
(OPTIONAL FEATURE)
Inform admin staff to reprioritize facility and rearrange tow pass
DASHBOARD to show vehicle under the status
TOWING ARRANGEMENT DONE
(using API GET from backend)
Admin Arrang for towing
Towing type = Trailer?
select vehicles & group by trailer / car carrier
(Multiple Selection)
Towing type = Towtruck?
Select Available facility to send the vehicle
Tow Pass generated (WITH QR) and shared with Tow Truck Driver
Update status - Vehicle On The Way
Display in the dashboard (chart) with the vehicle under the status [Vehicle On The Way] against ETA
RECEIPT VEHICLE IN THE FACILITY
TRANSFER TO ANOTHER FACILITY
ENTER NEW FACILITY
QR PRINTED?
DISABLE THE OLD QR
Scan tow pass - redirect to form page & print operations QR code
Update status - Checked in
Forklift transfers Checked in vehicle to depollution area
Update status - Transferred to BO bay
Transfer time = BODY DISMANTLING (START) - DEPOLLUTION TIME (END)
Super QR - Capture timestamp (END)
Forklift transfers vehicle to dismantling area
UPDATE STATUS TO - SENT TO YARD
Transfer Time = FORKLIFT PICKUP TIME - BODY DISMANTLING END TIME
Forklift transfers vehicle to yard
Super QR - Capture timestamp (START)
General worker depollutes the vehicle
Super QR - Report timestamp (END)
Update status - Depolluted by depolluter
Depolluation duration = (DEPOLLUTION TIME (END) - DEPOLLUTION TIME (START)
Super QR - Report timestamp (START)
Update status - Dismantling In Progress
General worker dismantles the vehicle
Display in the LIST of vehicle under status [Dismantling In Progress]
Supervisor stops timer
UPDATE STATUS TO - Body Dismantling Done
Transfer Time = FORKLIFT PICKUP TIME - BODY DISMANTLING END TIME
Display in the LIST as vehicle ready to dismantle
WITH SEARCH FEATURE
Excavator driver Swatch & Unlocks vehicle to dismantle
Excavator driver dismantles the vehicle
Upload dismantled photo
UPDATE STATUS TO - VEHICLE DISMANTLED
EXCAVATOR DISMANTLING DURATION = Capture photo timestamp - dismantling start timestamp
Display in the LIST as vehicle ready to dismantle
WITH SEARCH FEATURE
UPDATE STATUS TO - VEHICLE DISMANTLED
EXCAVATOR DISMANTLING DURATION = Capture photo timestamp - dismantling start timestamp