DistanceGP2Y0A21YK

Generated by Doxygen 1.7.4

Fri Jan 13 2012 20:41:54

CONTENTS 1

| \sim | | |
|--------|----|------|
| U | mi | ents |

| 1 | Class Index | | | | |
|-----|---|--|--|--|--|
| | 1.1 | Class I | List | | |
| 2 | Clas | lass Documentation | | | |
| | 2.1 | 2.1 DistanceGP2Y0A21YK Class Reference | | | |
| | | 2.1.1 | Constructor & Destructor Documentation | | |
| | | 2.1.2 | Member Function Documentation | | |
| | | | | | |
| 1 | 1 Class Index | | | | |
| 1.1 | 1.1 Class List | | | | |
| He | Here are the classes, structs, unions and interfaces with brief descriptions: | | | | |

- 1

1

2

2 Class Documentation

DistanceGP2Y0A21YK

2.1 DistanceGP2Y0A21YK Class Reference

Public Member Functions

• DistanceGP2Y0A21YK ()

DistanceGP2Y0A21YK.cpp - Library for retrieving data from the GP2Y0A21YK IR Distance sensor. For more information: variable declaration, changelog,... see DistanceGP2Y0A21YK.h.

• void begin ()

Begin function to set pins: distancePin = A0.

• void begin (int distancePin)

Begin variables.

• int getDistanceRaw ()

getDistanceRaw(): Returns the distance as a raw value: ADC output: 0 -> 1023

• int getDistanceVolt ()

getDistanceVolt(): Returns the distance as a Voltage: ADC Input: 0V -> 5V (or 0V ->
3.3V)

• int getDistanceCentimeter ()

getDistanceCentimeter(): Returns the distance in centimeters

boolean isCloser (int threshold)

isCloser: check whether the distance to the detected object is smaller than a given threshold

• boolean isFarther (int threshold)

isFarther: check whether the distance to the detected object is smaller than a given threshold

• void setAveraging (int avg)

setAveraging(int avg): Sets how many samples have to be averaged in getDistance-Centimeter, default value is 100.

void setARefVoltage (int refV)

setARefVoltage:set the ADC reference voltage: (default value: 5V, set to 3 for 3.3V)

2.1.1 Constructor & Destructor Documentation

2.1.1.1 DistanceGP2Y0A21YK::DistanceGP2Y0A21YK ()

DistanceGP2Y0A21YK.cpp - Library for retrieving data from the GP2Y0A21YK IR Distance sensor. For more information: variable declaration, changelog,... see DistanceGP2Y0A21YK.h.

Constructor

- 2.1.2 Member Function Documentation
- 2.1.2.1 void DistanceGP2Y0A21YK::begin ()

Begin function to set pins: distancePin = A0.

2.1.2.2 void DistanceGP2Y0A21YK::begin (int distancePin)

Begin variables.

- int _distancePin: number indicating the distance to an object: ANALOG IN
- int _transferFunctionLUT3V: Transfer function Lookup Table (for 3.3V reference value)
- int _transferFunctionLUT5V: Transfer function Lookup Table (for 5V reference value) When you use begin() without variables standard values are loaded: A0

```
2.1.2.3 int DistanceGP2Y0A21YK::getDistanceCentimeter ( )
```

getDistanceCentimeter(): Returns the distance in centimeters

2.1.2.4 int DistanceGP2Y0A21YK::getDistanceRaw ()

getDistanceRaw(): Returns the distance as a raw value: ADC output: 0 -> 1023

2.1.2.5 int DistanceGP2Y0A21YK::getDistanceVolt ()

<code>getDistanceVolt():</code> Returns the distance as a Voltage: ADC Input: 0V -> 5V (or 0V -> 3.3V)

2.1.2.6 boolean DistanceGP2Y0A21YK::isCloser (int threshold)

isCloser: check whether the distance to the detected object is smaller than a given threshold

2.1.2.7 boolean DistanceGP2Y0A21YK::isFarther (int threshold)

isFarther: check whether the distance to the detected object is smaller than a given threshold

2.1.2.8 void DistanceGP2Y0A21YK::setARefVoltage (int refV)

setARefVoltage:set the ADC reference voltage: (default value: 5V, set to 3 for 3.3V)

2.1.2.9 void DistanceGP2Y0A21YK::setAveraging (int avg)

setAveraging(int avg): Sets how many samples have to be averaged in getDistance-Centimeter, default value is 100.

The documentation for this class was generated from the following files:

- /home/jeroen/.dropboxstorage/Dropbox/11-arduino/libraries/GoogleCode_gp2y0a21yk-library/DistanceGP2Y0A21YK/DistanceGP2Y0A21YK.h
- /home/jeroen/.dropboxstorage/Dropbox/11-arduino/libraries/GoogleCode_gp2y0a21yk-library/DistanceGP2Y0A21YK/DistanceGP2Y0A21YK.cpp

Index

```
begin
    DistanceGP2Y0A21YK, 2
DistanceGP2Y0A21YK, 1
    begin, 2
    DistanceGP2Y0A21YK, 2
    getDistanceCentimeter, 2
    getDistanceRaw, 2
    getDistanceVolt, 2
    isCloser, 2
    isFarther, 2
    setARefVoltage, 2
    setAveraging, 3
getDistanceCentimeter
    DistanceGP2Y0A21YK, 2
getDistanceRaw
    DistanceGP2Y0A21YK, 2
getDistanceVolt
    DistanceGP2Y0A21YK, 2
isCloser
    DistanceGP2Y0A21YK, 2
isFarther
    DistanceGP2Y0A21YK, 2
setARefVoltage
    DistanceGP2Y0A21YK, 2
setAveraging
    DistanceGP2Y0A21YK, 3
```