**CPPC 18/L**

COMPUTER NETWORK & SECURITY

**ACTIVITY No.7**

**FTP (File Transfer)**

**Submitted by:**

**LOGATOC, APRIL FOILA JOY M.**

BS CpE 3B

**Submitted to:**

**ENGR. JAN ERROL MAMPUSTI**

Subject Professor

## I. Objectives

- To enable the FTP service on a server.
- To create a user account that can access files through FTP.
- To understand how file transfer works between a client PC and a server.
- To upload and download files using FTP commands.
- To verify if the FTP server can successfully receive and send files within the network.

## II. Materials

- Cisco Packet Tracer
- 1 Server
- 1 Switch
- 2–3 PCs
- Laptop
- Copper Straight-Through cables

## III. Procedures

### 1. Build the Network Topology

- Open Cisco Packet Tracer.
- Add the required devices in the workspace:
  - 1 Server
  - 1 Switch
  - 2–3 PCs
- Connect the devices using Copper Straight-Through cables:
  - PC to Switch
  - Server to Switch
- Make sure that all devices are properly connected and the links are active.

### 2. Configure the Server IP Address

- Click the Server.

- Go to Desktop.
- Open IP Configuration.
- Set the server with the following IP configuration:
  - IP Address: 192.168.1.1
  - Subnet Mask: 255.255.255.0
- This IP address will be used by the PCs to connect to the FTP server.

**3. Enable FTP Service**

- Click the Server.
- Go to the Services tab.
- Select FTP.
- Turn the FTP service ON.
- This will allow the server to accept FTP connections from the client PCs.

**4. Create an FTP User Account**

- In the FTP settings, create a user account for accessing the server.
- Enter the following login details:
  - Username: foilah
  - Password: foilah123
- Click Add to save the user account.
- This account will be used when logging in to the FTP server through the command prompt.

**5. Configure the PC IP Addresses**

- Click each PC one by one.

- Go to Desktop.
- Open IP Configuration.
- Choose Static IP configuration.
- Set the IP address of each PC:
  - PC0
    - IP Address: 192.168.1.10
    - Subnet Mask: 255.255.255.0
  - PC1
    - IP Address: 192.168.1.11
    - Subnet Mask: 255.255.255.0
  - PC2
    - IP Address: 192.168.1.12
    - Subnet Mask: 255.255.255.0
- Make sure that all PCs are in the same network as the server.

**6. Create a Text File on the PC**

- Click a PC.
- Go to Desktop.
- Open Text Editor.
- Type any sample content inside the text editor.
- Click Save As.
- Save the file as:
  - heal.txt
- This file will be used for testing the FTP upload and download process.

**7. Connect to the FTP Server**

- Go to Desktop on the PC.
- Open Command Prompt.
- Type the following command:
  - ftp 192.168.1.1
- Enter the login credentials:
  - Username: foilah
  - Password: foilah123
- Once logged in successfully, the PC is now connected to the FTP server.

**8. Upload the File to the Server**

- In the FTP prompt, type:
  - put heal.txt
- Wait until the upload process is completed.
- To check if the file was uploaded:
  - Click the Server.
  - Go to Services.
  - Open FTP.
  - Check if heal.txt appears in the file list.

**9. Download the File from the Server**

- In the FTP prompt, type:
  - get heal.txt
- Wait for the download process to finish.
- A successful transfer message confirms that the file was downloaded from the server.

## IV. Conclusion

The activity showed how FTP can be used to transfer files between a client computer and a server in Cisco Packet Tracer. By enabling the FTP service, creating a user account, and using the put and get commands, the text file was successfully uploaded to and downloaded from the server. This proves that FTP is useful for file sharing within a network and confirms that the FTP server was properly configured and functioning correctly.

## V. Documentation







Server0
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
PRP
FTP
Service
On
Off
User Setup
Username
Password
Write
Read
Delete
Rename
List
Username
Password
Permission
1
cisco
cisco
RWDNL
Add
Save
Remove


Server0
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
PRP
FTP
Service
On
Off
User Setup
Username
foilah
Password
foilah123
Write
Read
Delete
Rename
List
Username
Password
Permission
1
foilah
foilah123
RWDNL
Add
Save
Remove


PC0
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.10
Subnet Mask
255.255.255.0
Default Gateway
0.0.0.0
DNS Server
0.0.0.0


PC1
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.11
Subnet Mask
255.255.255.0
Default Gateway
0.0.0.0
DNS Server
0.0.0.0


PC2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.12
Subnet Mask
255.255.255.0
Default Gateway
0.0.0.0
DNS Server
0.0.0.0


PC2
Physical
Config
Desktop
Programming
Attributes
Text Editor
X
File
Lord I surrender everything to you, I'm not one of your strongest soldier.


PC2
Physical
Config
Desktop
Programming
Attributes
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ftp 192.168.1.1
Trying to connect...192.168.1.1
Connected to 192.168.1.1
220- Welcome to PT Ftp server
Username:foilah
331- Username ok, need password
Password:*********
230- Logged in
(passive mode On)
ftp>put heal.txt
Writing file heal.txt to 192.168.1.1:
File transfer in progress...
[Transfer complete - 74 bytes]
74 bytes copied in 0.051 secs (1450 bytes/sec)
ftp>


PC1
Physical
Config
Desktop
Programming
Attributes
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ftp 192.168.1.1
Trying to connect...192.168.1.1
Connected to 192.168.1.1
220- Welcome to PT Ftp server
Username:foilah
331- Username ok, need password
Password:*********
230- Logged in
(passive mode On)
ftp>get heal.txt
Reading file heal.txt from 192.168.1.1:
File transfer in progress...
[Transfer complete - 74 bytes]
74 bytes copied in 0.001 secs (74000 bytes/sec)
ftp>


Server0
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
PRP
FTP
Service
On
Off
User Setup
Username
Password
Write
Read
Delete
Rename
List
Username
Password
Permission
1
foilah
foilah123
RWDNL
Add
Save
Remove
File
1
heal.txt